

Technical description for the communication between BlueRange APP and BlueRange Node

Inhalt

1.	History	4
2.	Abbreviations used in this document.....	11
3.	Requirements on BlueRange Mesh	11
4.	Introduction	13
5.	Definitions	14
6.	Descriptions of the System configuration.....	15
6.1	Page 'Manage Devices'	15
6.1.1	'Add new BR device'	15
6.1.2	'Add Philips Hue device'	16
6.1.3	'Delete Devices'	16
6.2	Page 'Setup Device'	16
6.2.1	'Select device'	16
6.2.2	'Identify Device + Driver'	16
6.2.3	'Addressing'	17
6.2.4	'Connect to System Luminaire'	17
6.2.5	'Sensor configuration'	17
6.2.6	'Input configuration'	18
6.2.7	'Change Device "Name"'	18
6.2.8	'Device Info'	18
6.2.9	'LINA AUTO SETUP'	18
6.3	Page 'Sensor configuration'	19
6.3.1	Read Sensor Parameters	19

6.3.2	Write Sensor Parameters	19
6.4	Page 'Input configuration'	20
6.4.1	Teach In BT Switches	20
6.4.2	Device Inputs	20
6.5	Page 'Scene configuration'	21
6.6	Page 'EVENT configuration'	22
6.7	Page 'Upgrade Premium Version'	23
6.8	Page 'Manage Accounts'	24
6.8.1	'Create User'	24
6.9	Page 'Setup Sequence / Timer:'	25
7.	Descriptions for Touch4Light page (user operating page)	26
8.	Appendixes	26
8.1	Appendix A: BT communication frame description.....	27
8.2	Appendix B: Command description App → MWAYfirmware → VSfirmware.....	29
8.3	Appendix C: Reaction List description.....	48
8.4	Appendix D: List of Node Types	51
8.5	Appendix E: Event (Input) Types.....	51
8.6	Appendix F: List of Packet- and Destination-Types in MsgHeader	56
8.7	Appendix G: Definition of User Dataset (for User 2D Code Preparation)	56
8.8	Appendix H: Definition of the System Luminaire Types.....	57
8.9	Appendix I: Msg_Status	57
8.10	Appendix J: Physical luminaire type feature.....	59
8.11	Appendix K: Possible EventType / ActionType Combinations.....	60
8.12	Appendix L: Command description BR firmware ← BT firmware	61
8.13	Appendix M: Use cases	62
8.13.1	BT Button Type and destinationType	62
8.13.2	Lightcontrol and motion monitoring	64

8.13.3	Lightregulation	65
8.14	Appendix N: CRC8	66
8.15	Appendix O: En- & Decryption	68
8.16	Appendix P: Sequence table definition	69
8.17	Appendix Q: Time calculation according DALI	70
8.18	Appendix R: Timer Handling	72
8.19	Appendix S: Testing the sensor (DUT) in the tester	73
8.20	Appendix T: StartUp nodeDevice and lightlevel on a virtLum	75
8.20.1	Power Ready	75
8.20.2	Default Scene	75
8.20.3	Virtual Luminaire, Functional Group (FG)	75
8.20.4	Changing reactionTab during user event configuration	76
8.21	Appendix U: virtual luminaire data	76
8.22	Appendix V: moveSenseAct	77
8.23	Appendix W: Search modes	78
8.24	Appendix X: Slider Type	79
8.25	Appendix Y: Bootloader	80
8.26	Appendix Z: VS Internal Commands for Tester	83

1. History

<u>Date</u>	<u>Ver- sion</u>	<u>Page</u>	<u>Description</u>
2017 Braunschmid(Br), Zehender (Ze)	1..7 (draft)	init	Initial versions
21-09-2017, Nie- mann(Ni)	8 (draft)	Appendixes	Changed Para and response scheme on some commands, added new command ' <i>NodeDeleteVirtualLum</i> ', changed ' <i>update level</i> ' to 16-bit
27-09-2017, Ni	9 (draft)	Appendix B	A system time has no ID since it is generic
		Appendix E	Parameter change Event message
		Appendix K	Event and action type combination, preliminary
05-10-2017, Ni, Ze	9.1	Appendix N,O	Reject "draft", added CRC8 and Encryption (XTEA) description
05-10-2017, Ze	10		Included 'Requirement for Bluerange Mesh'
15-10-2017, Ze	10.1	Appendix P,Q	Sequence Table
16-10-2017, Ni, Ze	10.2		Implementation details, corrections
19-10-2017, Ni, Ze	11		New action types AT_START_SEQUENCE, AT_STOP_SEQUENCE, new event type ET_TIMER, ET_REGULATION and their respective commands, Added Status byte in <i>SetNodeVirtualLumData</i>
23-10-2017, Ze	12		On m-way request, changed some formulation in requirements
25-10-2017, Ze	12.1		More formulation changes for m-way
26-10-2017, Ze	13		Better specification for HCI mode
26-10-2017, Ze	14		Removed '....resulting from IP infringement claims.'
15-11-2017, Ni	14_1	Appendix B,C,I	<p>Appendix B:</p> <p>Response of command <i>NodeCreateVirtualLum</i> has been adjusted; Command <i>Set/GetNodeVirtualLumData</i> contains passive / active etc. brightness % values instead levels: has been adjusted to one byte. This is because of dimming processes of RGBWAF lightLevel channels which are based and calculated via brightness % values; Deletion of a physical lum channel in a virtual luminaire: Byte 1, bit 7 of command <i>SetPhysLumChannel</i> has been adjusted to do so; Introducing command <i>GetVirtLumLevel</i>. Helpful for slider sync on HandyApp;</p> <p>Appendix I:</p> <p>Some MSG_STATUS_xxx has been added;</p> <p>Chapter 6.5:</p> <p>Corrected log10 formula; Command <i>GetColorControl</i> and <i>SetNodeScene</i>: value range of brightness is 0...254</p> <p>Appendix C:</p> <p>Light Reaction Dim Brightness / Color has been adjusted; max. ActionType Parameter 6</p>

24 -11-2017, Buelow			Spelling corrections and improvements (corrections of drawings). Added M-Way support for testing a DUT in the tester in chapter "Requirements on BlueRange Mesh.
27-11-2017 27-11-2017, Ni 28-11-2017, Ze 28-11-2017, Br 28-11-2017, Ni, Ze		Appendix B 4. Introduction 6.4.1 6.3 Appendix K Appendix C Appendix E	Moved the added informations of "M-Way support for testing a DUT in the tester" from 24-11-2017 to a new chapter "Appendix S" Added <i>SetScene2VirtLum</i> Added <i>GetSensorData</i> Document Titel TeachIn procedure must be approved by VS. Command changed Reworked ActionType_VirtLumChannelSet, Parameter changed Rejected ET_LIGHT_REGULATION, rejected PassiveArea Action
07-12-2017, Ni	15	Appendix B	Added description for command requirements changed PacketID size from 2 Bytes to 1 Byte changed syntax of AT_LIGHT_REGULATION in AT_LIGHT_REGULATION_MODE
14-12-2017, Ni 19.12.2017, Ni 20.12.2017, Ni 02.01.2018,Ni 11.01.2018,Ni 24.01.2018,Ni 24.01.2018,Ni	16 17	Appendix E Appendix C Appendix E Appendix B Appendix E,P Appendix B	added response to an EventMsg justify description for ET_LIGHT_LEVEL, Para 0 corrected possible values for virtLumNo[1..16] ET_REGULATION: added initLR=4 for initialisation of a foreign node with several virtLum's who joins light regulation for light outputs <i>SetScene2VirtLum</i> : added possible para val Event-Msg will response as a UART-Response only Action „virtLumChannelSet“ now with „param5=start Scene“. Allows assignment of lightlevel to a virtLum at light regulation start Added a "Note" for fallback scene 1 Adjusted scene sequence Added "In general" descriptions of command parameter
	18	Appendix B Appendix E	NodeIdentifyPhysLum: added para addr val 0xffff for deviceLED SetNodeSystemKey: Parameter SystemKey "0" resets all node data New Event ET_POWER_READY, which will be sent by VSfirmware
26.01.2018, Ze 31.01.2018, Ni 02.02.2018, Ni	19	Appendix R Appendix C Appendix B Appendix T	Added a table with possible Timer entry data combinations Added descriptions for action types Changed ActionType Param: now 5 parameter Added "Manual mode" for AT_LIGHT_REGULATION_MODE SetSeqEntry Param Byte 3 and 4 put together in byte 3 to save memory SetNodeReactionEntry: added "user" possible values

		Appendix E	Added Start up (Power on) behaviour Added notes, e.g. Encryption type is UserKey if send from HandyApp, otherwise SystemKey
07.02.2018,Ni	20	Appendix B	Set-/GetInput: Added value range for Byte 0 SetNodeVirtualLumData: Byte 3 “state” has been declared as free and will be ignored in VSfirmware SetNodeVirtualLumData: dimSpeed in units of 700ms Add a general note GetNodeVirtLumData: byte 3 renamed in “modeState” GetNodePhysLums: added Status info, adjusted response data SetColorControl: jetzt zusätzlich mit UserKey Verschlüsselung GetNodeStatus: corrected description for byte 5 Added / corrected MSG_STATUS 0x13..0x19, 0x20,0x21,0x22,0x23,0x24,0x80 SceneSequence STOP interpretation 0x7E Corrected Parameter for AT_SEQUENCE_PROCESS Rejected ET_SEQUENCE_PROCESS Added notes, adjusted event nums Corrected “numPara”
14.02.2018,Ni		Appendix I Appendix P	
19.02.2018, Ni		Appendix E Appendix C	
07.03.2018, Ni	21	Appendix U Appendix I Appendix B	virtLum data explanation added more MSG_STATUS_xx added a general note: If a rxd (uart) message frame fails: it may not possible to select between a command and an event. In this case a simple One-byte-uart response will be delivered with an appropriate MSG_STATUS content. Attached a Note to min Brightness Added AT_SLIDER_CONTROL Added ET_SLIDER_CONTROL
16.03.2018, Ni		Appendix C Appendix E	
26.03.2018, Ni	22	Appendix B	Set-/GetVirtualLumData: replaced “light regulation active” with “moveSenseAct” SetTimer variable “timestamp” now renamed in “time” Added movement sensor action behaviour, <u>moveSenseAct</u> Added search mode behaviour Added detail “SetTimer” examples
03.04.2018, Ni		Appendix V Appendix W Appendix R	
05.04.2018, Ni	23	Appendix E Appendix X Appendix C	Changed behaviour of ET_BT_BUTTON parameter inputNum always 0 Added slider type definitions Added para “sliderType” for AT_SLIDER_CONTROL Renamed AT_LIGHT_REGULATION_MODE in AT_LIGHT_CONTROL Added command GetNewSearchData Added MSG_STATUS_PHYS_LUM_ADDR_ALREADY_USED 0x28 Renamed MSG_STATUS_INVALID_PHYS_LUM_NUM in *_PHYS_LUM_ADDR Added new event type ‘ET_EXT_BEACON’ for handling of external beacons. Added new action Type ‘AT_BEACON_STATE’ to switch internal beacon function On/Off/Toggle. Added command ‘SetBeaconState’ (together with ‘AT_BEACON_STATE’).
Ze		Appendix B Appendix I Appendix E Appendix C Appendix L	

		Appendix D Appendix M	Added new Node type 'NT_VS_CONNECT_ME'. Corrected BT button handling according inputNum parameter (always 0)
10.04.2018, Ni	24	Appendix E Appendix B,C,U,V Appendix P	Added comments for EventType, description for ET_CHANGE_SCENE modified moved "moveSenseAct" to AT_LIGHT_CONTROL added further explanation
20.04.2018, Ni	25	Appendix B Appendix C Appendix E Appendix D	Corrected SetNodevirtLumData, Added more explanations for SetInput Byte4,5 Renamed AT_VIRT_LUM_CHANNEL_SET into AT_LIGHT_REGULATION, reduced parameter Added more explanations regarding eventTab & reactionTab Added more explanations for node types
04.05.2018, Ni	26	Appendix B Appendix K Appendix R Appendix C Appendix I	Added a general node regarding "Scene" Command TransmitFirmwareData: Block size has been set to 256 Added info ET_SYSTEM_TIME: unused for now SetTimer: added enable/disable flag Changed Note: tab overwriting possible Command and Response of NodeCreateVirtualLum has been redesigned changed Event / Action Matrix added an enable/disable flag for TimerTab, renamed "Repeat Field" in "Control Field" changed parameter configuration for AT_TIMER added MSG_STATUS_OVERWRITE_WARNING distinguish between errors and warnings (>=0xE0)
07.05.2018, Ni	27	Appendix B Appendix K Appendix Y	Added GetNodeStatus Response Status: Bit1 Added a Note: The response of a command leads up with the commandNo always and follows the MsgStatus with Byte 0 Rejected combination ET_TIMER with AT_DIM_UP_DOWN... Added "Bootloader" info
14.05.2018, Ni	28	Appendix B Appendix I	Added array count in response of GetNodeVirtLums Added "ID" in name of encryption type in address field Set-/GetNodeReactionEntry: changed interpretation of Byte7, now UserkeyID Added 6 new MSG_STATUS*
23.05.2018, Ni, Ze	29	Appendix I Appendix Z Appendix B Appendix Y	Added / Corrected new MSG_STATUS* regarding firmware update and other commands. Added detail description of MSG_STATUS Added description of VS internal commands for tester Added a note to NodeIdentifyPhysLum, added new command "Debug" Update VSfirmware download
05.06.2018, Ni	30	Appendix I Appendix Y	Added MSG_STATUS_PREMIUM_FAILED, MSG_STATUS_EVENT_TAB_ERR Update VSfirmware download format description

13.06.2018, Ni	31	Appendix B Appendix I	VSfirmware download commands always with node key encryption Added new command "GetVersion" Changed a parameter of command NodeIdentifyPhysLum edited MSG_STATUS
20.06.2018, Ni	32	Appendix D Appendix B	Changed wording Added MSG_STATUS_RXD_PACKET_ERR Changed Note: The response of a command leads up with the commandNo, following MsgStatus, following 16-Bit updateLevel (MSB first, LSB second) Cmd "GetNodeUpdateLevel" has been rejected
25.06.2018, Ni	33	Appendix B Appendix D	Cmd "GetNodeUpdateLevel" has been re-integrated Cmd "GetVersion" now with SystemKey encryption Response of "GetNodeStatus" includes max. reactionTab entries in addition changed description NodeType
26.06.2018, Ni 28.06.2018, Bue	34	Appendix M Definitions Appendix C Appendix B Appendix I Appendix E Kap.6.7	Add explanations: use case of light control and regulation Add definition for a "scene" Add param5=sceneNo for AT_LIGHT_CONTROL Response auf GetNodeStatus liefert auch Anzahl möglicher User (maxUser) Added MSG_STATUS_LIMIT_REACHED Changed description MSG_STATUS_OVERWRITE_INFO EV_BT_BUTTON_X can have variable inputNum[0..255] Correct wording virtual channels in "virtual luminaires"
04.07.2018, Ni	35	Appendix B Appendix C Appendix I In general Appendix E Appendix A	SetNodeReactionEntry has UserkeyID 2-251, changed SetInput / GetInput AT_TIMER has been rejected Added MSG_STATUS_DECRYPTION_FAILED, MSG_STATUS_WRONG_USER_KEY_ID Changed ET_BT_BUTTON_x to ET_BT_BUTTON_TYPE_x in various descriptions. Instances of this type works thru "inputNum"...^ Changed #defines of all Events ! DestinationType has been defined
10.07.2018, Ni	36	Use cases Appendix B Appendix T Appendix F	BT Button and destinationType SetUser pos can be delete thru 0xff SetScene2VirtLum(0xFF,SceneNum) allows settings a LLScene to all available virtLums Detail description StartUp of deviceNode Detail description of packetType, destinationType
16.07.2018 24.07.2018	37	Appendix B All Appendix B	changed GetInput-Response (added "max Instanz") changed wording: BTfirmware="VSfirmware", BRfirmware="MWAYfirmware" Command Debug: changed Debug type 3 (re-program DALI-Groups)

		Appendix C	AT_SLIDER_CONTROL added LLScene
04.09.2018, Ni	38	Appendix C Appendix X Appendix K	AT_LIGHT_SCENE added param4 “mode” New SLIDER_TYPE_LIGHT_REGULATION defined Added combination ET_BUTTON \leftrightarrow AT_LIGHT_REGULATION Added combination ET_SLIDER_TYPE \leftrightarrow AT_LIGHT_REGULATION
10.09.2018, Ze 11.09.2018, Ni 14.09.2018, Ze	39	Appendix E Appendix B Appendix I	Added ET_IO_BUTTON parameter description to table Added new Command SetBrightnessRef Added MsgStatus MSG_STATUS_WRONG_NODE_TYPE 0x43
27.09.2018, Ni 05.10.2018, Ni 08.10.2018, Ni 18.10.2018, Ni	40	Appendix K Appendix I Appendix P Appendix B	Some more explanations regarding light regulation Added a warning: MSG_STATUS_LUMINAIRE_INCOMPATIBEL_SCENE 0xe3 Changed Note: Stopping a sequence loop is possible via a proper reactionTab entry only GetSensorData call now with SystemKey
19.10.2018, Ni 23.10.2018, Ni 24.10.2018, Ni	41	Appendix B Appendix I Appendix E	Description for SetBrightnessRef: Start light regulation GetNodeStatus Byte4, added Bit2: light regulation Tasks active / inactive GetNodeStatus Byte4, added Bit3: movement Task active / inactive SetBrightnessRef: Para 0xffff turns off light regulation Added a warning MSG_STATUS_MISSING_CONDITION 0xe4 Added correct description for ET_LIGHT_LEVEL, ET_REGULATION
06.11.2018, Ze 07.11.2018, Ni	42	Appendix Z Appendix C Appendix V	Added UART Test Reduced Parameterlist from 5 to 4 Bytes. Changed for AT_LIGHT_CONTROL, AT_EVENT_MANIPULATION, AT_DIM_UP_DOWN_COLOR moveSenseAct: rejected “Auto” and “Auto and On”
12.11.2018, Ni 11.12.2018, Ni	43	Appendix B Appendix C Appendix R Appendix E Appendix K Appendix P	GetNodeStatus, Byte1, Bit4 declares a valid actual timestamp SetTimeStampField renamed in SetLocalTime , data timestamp added Added CMD_CHECK_FW_COMPATIBILITY GetTimeStamp renamed in GetLocalTime Parameter AT_LIGHT_SCENE “Event on target” rejected Changed AT_SEQUENCE_PROCESS para2 SetTimer repetition monthly, yearly not required any more Changed due to DT8, added ET_SEQUENCE Description for repetitive TimerEvents reduced for monthly, yearly ET_SYSTEM_TIME_INFO has been rejected and replaced with ET_TIMER in eventTab[] Added ET_SEQUENCE Changed description for sequence end behavior
12.12.2018, Ni 20.12.2018, Ni 02.01.2019, Ni	44	Appendix B Appendix R	Changed parameter CMD_CHECK_FW_COMPATIBILITY Command SetSeqEntry, description byte 0 Modified AT_SEQUENCE_PROCESS para1 Timer Handling description

16.01.2019, Ni		Appendix I	MSG_STATUS_PREMIUM_FAILED rejected
22.01.2019, Ni	45	Appendix J Appendix B Appendix C Appendix J	Changed #defines according TechSpec42 for keeping MWAY data model Command SetSeqEntry Byte 3 has been re-changed according TechSpec42 AT_SEQUENCE_PROCESS params has been re-changed according TechSpec42 Added description details
15.02.2019, Ni	46	Appendix C Appendix X Appendix B Appendix E Appendix I:	Changed Note(1): A reaction of ET_SLIDER with AT_SLIDER_CONTROL acts on a FunctionalGroup which owns a scene number itself. A scene number is therefore not necessary in the App for now, but needs to delivered for message length. A scene number may be used in the future in conjunction with ET_SLIDER_CONTROL i.g. configuration of a scene... Add slider type spreadsheet for possible combinations of sliderType, ET_SLIDER and ET_SLIDER_CONTROL Added new commands "ConfigMoveSendInterval", "ControlWriteFlash", "ControlEventSend", "IgnoreSetReactionConstraints" ET_SENSE_MOVEMENT: changed parameter Byte 1 Added MSG_STATUS_IGNORE_SET_REACTION_CONSTRAINTS (0xe0)
04.03.2019, Ni	47	Appendix B	Rejected "ControlWriteFlash", "ControlEventSend" after Telco 19.02.2019
19.03.2019, Ni	48	Appendix B Appendix T Appendix J Appendix I	Rejected commands <i>GetNodeLimitID</i> , <i>SetLimitKey</i> , <i>SetHiddenKey</i> Cmd SetBrightnessRef para max. value changed Changed description of functional group lightlevel behavior after reset Changed parameter Added MSG_STATUS_INCOMPATIBEL_VIRT_LUM (0x33)
03.04.2019, Ni	49	Appendix I	Added MSG_STATUS_GROUP_ADDR_REJECTION_FAILED (0x20)
10.05.2019, Ni	50	Appendix D Appendix E Appendix B	Added FirmwareID=1 for NodeType CONNECT_PLUS Added additional ET_REGULATION para GetNodeStatus, Byte 11: represents count of DALI groups SetBrightnessRef new selection for user ref value New command GetNodeVirtLumLL(48)
13.05.2019, Ni	51	Appendix B Appendix I	Adapted command GetNodeVirtLumLL(48) to GetNodeVirtualLums2(48) New command "GetBrightnessSensorRef"(49) New command "GetNodePhysLum2"(50) with reduced rsp length New command "SetTableId (51) New command "GetTableId (52) New MSG_STATUS_LOCAL_TIME_INVALID(0x44), MSG_STATUS_LR_ACTIVE(0xe5), MSG_STATUS_RSP_DATA_OUT_LENGTH_EXCEEDS((0x45)

	Appendix E	ET_SLIDER with additional control parameter for initial light regulation
--	------------	--

2. Abbreviations used in this document

BT	Bluetooth
BR	Bluerange
ET_	EventType
AT_	ActionType
RSP_	Response
Cmd	Command
App	Application
Virt	Virtual
Lum	Luminaire
MSB	Most significant bit
LSB	Least significant bit
Phys	Physical

3. Requirements on BlueRange Mesh

Main topics on the mesh network described in the following chapters of this document:

- The mesh firmware does the complete EnOcean BT button handling on a node (PTM215B, max. 4 units/16 buttons per mesh node) and signals it to VS Firmware via UART incl. Button Key handling etc....
- FW Upgrade via Mesh for the Bluetooth module transferred via GATT and UART (target addressed or complete mesh network).
- FW Upgrade via Mesh for VS μ C transferred via GATT and UART (target addressed or complete mesh network).
- The mesh transfers Data according Spec. [Appendix A: BT communication frame description](#)
- Implementing of the GATT Protocol. (*will be handled by M-Way*)
- Adjustment of the mesh parameter of the mesh network for light technology requirement (M-Way will optimize Hop Times <20ms, means < 1.28 s for 64 in row connected nodes).
- Mesh network connections should be optimized for short reaction times. (*will be handled by M-Way*)
- Transfer von GATT Nachrichten an UART. (*will be handled by M-Way*)
- The Power down and restart behavior will be optimized by M-Way. The NodeID's will be stored and maintained.
- Offline commissioning with QR-Code of the mesh network. (*will be handled by M-Way*)
- Possibility to add new nodes to an existing mesh network through mesh network. (The GATT connection to existing node has to be used).
- Access to GATT with password in QR-Code.
- Mesh network should handle a timestamp. (*will be handled by M-Way*)

- Auto-Packet Splitting & Reassembling. (*will be handled by M-Way*)
- Possibility to adjust the mesh parameter ,Count of simultaneous connection in mesh‘ (Standard 4, up to 7) .
- M-Way supplies a simulator which fits to the mesh firmware.
- Beacons should be able to activate / deactivate via UART/GATT command.
- Commissioning of the nodes via the mesh.
- The mesh should use an unique, unchangeable Mesh-ID. (*will be handled by M-Way*)
- The mesh network should handle up to 400 nodes.
- Source Code and Build-Environment should be available for VS.
- The mesh parameter should be able to request via APP.
- The Node should use FiFo handling.
- The Firmware has to work and run on a module with RF52832 chipset (MBN52832).
- Both parties agree to aim a common SIG certification. Both parties have to support the SIG certification process and necessary adoptions if relevant.
- The ‘Direct Test Mode’ of the **nRF52** must be able to activate via UART command (For Test purposes and certifications). If necessary (e.g. for approvals) a separate firmware file with full HCI support should be available.
- The Source-Code of the Mesh-Firmware and also the App must be available for VS.

4. Introduction

This Document describes the communication between the BlueRange APP and the connected BlueRange Node. It is based on the [BlueRange APP description](#) from Mr. Lade.

This Document is intended to provide an overview of the needed sequences and commands planned to be used inside the VS-Event-Mesh.

This Document is now on a working stage as part of the contract and will only be changed if technical failure is detected and require a change.

5. Definitions

Node	A Node is our BT device, per example the Multisensor XS.
SYSTEM	A set of Nodes which will work together (Mesh network).
NODE KEY	This 16 Byte key is used for first configuration of a node, created in VS Production and delivered in the Node QR code.
Node QR Code	QR code with data for first configuration of the Node. It includes Node Key, serial number of the Node, device name etc.
SYSTEM KEY	This Key (16 Byte) is used for encrypting all system and admin communication in the mesh network. The SYSTEM Key will be created by the App at SYSTEM creation.
USER KEY	This Key (16 Byte) is used for encryption of the user communication between the node and connected mobile device (APP). This Key will be created by the APP if a user for the SYSTEM will be created.
User QR Code	A QR code which includes all necessary data for importing a user to the APP.
Physical Luminaire	‘real’ luminaire connected to the node (ex. DALI can be up to 64 luminaires)
System / Virtual Luminaire	A virtual luminaire is software interface to the real luminaire.
Encryption	We use the XTEA algorithm with different keys (SYSTEM, NODE or USER key) to encrypt our communication.
Update Level	is an up-counting number (0-65535) and will be used to handle the data synchronization between the mobile app(s) and the node(s). Each Node has its own update level. All Commands which are changes the configuration of the node will change the update level of this node. Before the app starts a configuration session, he has to read the update level of the node and compare it with the level stored in the mobile. If the update level in node is higher than the value stored in app, the app has to read the configuration again from the node.
BRnode software	The BRnode software module (M-Way) handles all Bluetooth communications (Mesh, BT switches and GATT connection to mobile devices) and transfers the BRmesh protocol msg's, within the BRnode hardware, to the BTnode software module via UART.

BTnode software

The BTnode software module (VS) receives / sends the msg's via UART and manages the inputs (sensors) and luminaires within the BRnode hardware.

Scene

is a lightlevel scene (LLScene). A virtual luminaire (or a system luminaire) can output a LLSce through its channels

6. Descriptions of the System configuration

All commands are described in [Appendix B](#)

6.1 Page 'Manage Devices'

Manage Devices

- **Add new BR device:** opens QR code scanner (scan 1 to all) cross check and mesh build works in the background (only for selected System / Mesh network)
 - **Add Philips Hue device**
 - **Add "name" or location** of new BT device as a must!
 - **Delete Devices** (from shown list with radio signal if connected) multiple possible, are you sure? (generate new sys key)
- > back Home

6.1.1 'Add new BR device'

Scanning Node QR Code.

Build GATT connection to BlueRange device according Info from Node QR Code.

Send command '[SetNodeSystemKey](#)' with Parameter 'System Key' to add BR device to SYSTEM. Parameter SystemKey "0" resets all node data (scenes, reaction entries, sequence entries, etc.)

Command should be encrypted with Node Key, which is included in Node QR Code.

Send '[GetNodeStatus](#)' to get all Info about the Node.

Send '[NodeSearchPhysLum](#)' to start a search for all, to the BR device connected, physically luminaries (DALI drivers)

Check periodically the state of the node by sending '[GetNodeStatus](#)' to detect if the search is finished or alternatively wait for the Event 'End of Phys Search'.

Send '[GetNodePhysLums](#)' to get all data from Node about found physical luminaries.

Note: The QR Code must at least contain the following information (the way of coding them into the QR Code has to be defined as soon as the content is fixed): Node Key, all Codes and information to establish a GATT connection, all information to connect to M-Way mesh.

6.1.2 'Add Philips Hue device'

Not implemented yet. Maybe will be implemented in a future version.

Setup Device

- **Select device**
selection from shown node list
with radio signal strength as
additional info
- **Identify Device LED + Drivers**
- **Addressing**
- **Connect to System Luminaire**
- **Sensor configuration**
- **Input configuration**
- **Change Device "Name"**
- **Device Info**

> back Home Setup



LINA

AUTO SETUP
Per Node device:

Do Addressing
+ Add all to one
System Luminaire
Tbd in detail

6.1.3 'Delete Devices'

Show the list of all devices . To delete the selected BR device from SYSTEM, **all** other nodes in the SYSTEM have to receive a new SYSTEM KEY with Cmd '[SetNodeSystemKey](#)' with their, in the SYSTEM stored, NODE KEY.

6.2 Page 'Setup Device'

6.2.1 'Select device'

Shows a list all available devices (nodes) with radio signal strength. A device should be selectable for further configuration.

6.2.2 'Identify Device + Driver'

Let all connected physical luminaires blink in x seconds interval to

identify the device.

Send command '[NodeIdentifyPhysLum](#)' with the Parameter

Byte 0-1 = #HFFF (broadcast = all luminaires) and Byte 2 (1 = Identify On / 0 = Identify Off) to switch Identify On or Off.

6.2.3 'Addressing'

Start physical Addressing of all physical Luminaires with Cmd ['NodeSearchPhysLum'](#) .

There are 3 Modes which must be selectable:

- Search Mode:
- 0 (Clear & Search) clear existing addresses and all gets new addresses
 - 1 (Search only New) Only units without short address will get a new short address
 - 2 (Keep & Search) same as Mode 1, but with additional check for duplicity of short addresses

Search Mode is a Parameter of the command above.

Wait while Addressing is running.

Check if finished by periodically checking the Node status with Cmd ['GetNodeStatus'](#) or by waiting on Event 'End of Phys Search'.

Show all found devices in a list.

6.2.4 'Connect to System Luminaire'

1. Make connections between Physical Luminaires and System Luminaire.
2. Create the System Luminaire with Cmd ['NodeCreateVirtualLum'](#) to get virtual luminaire number.
3. Depending on the wanted Luminaire Type (ex. Tuneable White Luminaire, RGB Luminaire, etc.) the APP sets the necessary count of channels' for the System Luminaire. Assign a System Luminaire channel to a Physical Luminaire address/number with Cmd ['SetPhysLumChannel'](#).

General the admin can

- Set new settings of the System Luminaire with Cmd ['SetNodeVirtualLumData'](#).
- Read the data of all created System Luminaire by Cmd ['GetNodeVirtualLums'](#).
- Read the configured channels of the one System Luminaire num by Cmd ['GetVirtualLumChannels'](#).
- Read the Settings of one System Luminaire num with Cmd ['GetNodeVirtualLumData'](#).

6.2.5 'Sensor configuration'

[See](#) Sensor configuration page

6.2.6 'Input configuration'

This changes the input configuration of the selected device. See [here](#).

6.2.7 'Change Device "Name"'

This changes the virtual name of the selected device.

6.2.8 'Device Info'

This shows all Information that's available about the selected device.

6.2.9 'LINA AUTO SETUP'

The 'LINA Auto Setup' sets an automatic standard configuration on the selected device.

It starts the following configuration steps:

- Addressing all physical Luminaires with Cmd '[NodeSearchPhysLum](#)' with Search Mode 0 (Reset & Search).
- Add all physical Luminaires to System Luminaire with procedure shown [here](#).

6.3 Page 'Sensor configuration'

Sensor configuration

- Adjust Parameters
for Daylight / Movement
with graphic adjustment diagram
- Maybe use camera for light level
- **Graphic assignment
together with M-Way**

> back Setup Home

6.3.1 Read Sensor Parameters

Read actual Sensor Data by Cmd ['GetInput'](#)

6.3.2 Write Sensor Parameters

Changed values will be written by Cmd ['SetInput'](#)

6.4 Page 'Input configuration'

Input configuration

- Teach In BT Switches
 - Device Inputs (if existing)
- > back Setup Home

6.4.1 Teach In BT Switches

BT Switches have to be taught into the node.
(Paired BT connection with the node)

The Node must create an event which is then being routed
into the mesh network.

The Teach In procedure must be approved by VS.

6.4.2 Device Inputs

Read data of the Device Input by Cmd ['GetInput'](#).


Sets data of the Device Input by Cmd ['SetInput'](#).

6.5 Page 'Scene configuration'

Scene Configuration*

- For all possible 64 scenes
- Set scene "name"
- Adjust scene parameters
- **Graphic assignment together with M-Way**

> back Setup Home



All Level Sliders (vertical) will show a range of 0% to 100%. These percentage values have to be converted into 8 Bit values. For the Master Level Slider, we are using a linear conversion with following formula:

$$x = (100/254) * n \quad \text{where } x = \text{percentage value, } n = 8\text{-bit value}$$

The Channel Sliders (Ch1 ... Ch6) using a logarithm conversation as DALI definition:

$$x = \log_{10}^{(((n-1)/(253/3))-1)} \quad (\text{if } n = 0, \text{ then } x \text{ must be } 0 \text{ as well}).$$

The value 255 (0xFF) is reserved for 'Do not change'.

The Time Slider will show time in hour, minutes or seconds, depending on value. For conversion in a 8 Bit value, we use a range of 32 steps with formula described in [Appendix Q](#).


Scene Parameter can be read by Cmd **'GetNodeScene'**

Scene Parameter can be written back to Node by Cmd **'SetNodeScene'**.

To get a live visual feedback about the actual settings, the Cmd **'SetColorControl'** can be send to the Virtual Luminaire.

6.6 Page 'EVENT configuration'

EVENT Configuration / Binding and view from Luminaire side



Reaction Configuration is organized as a list with entries.


Actual Event / Input Configuration can read with Cmd ['GetInput'](#).

Actual Reaction Configuration can be read with Cmd ['GetNodeReactionEntry'](#).

Changed Event / Input Configuration can be written with Cmd ['SetInput'](#).

Changed Reaction Configuration can be written with Cmd ['SetNodeReactionEntry'](#).

EVENT Configuration / Binding of Control elements



Manipulation Event Configuration

Manipulation events have to be defined. Probably the same commands described above (with different parameters) can be used.

6.7 Page 'Upgrade Premium Version'

Detail Info of Premium features per Bluetooth node:

- Virtual Luminaires 4 > 16
- Physical address 8 > 64
- Users 2 > 4
- BT Switches 2 > 4
- Beacon 0 > 1

Purchase over In App Payment or over M-Way Cloud Service.

If system detects premium node this info page can disappear

For unlocking the Premium Version after payment, we have defined two commands:

Use Cmd ['GetNodeLimitId'](#) to get the Node specific payment data from Node. These data has to be sent to VS to get the Limit Key.

Use Cmd ['SetLimitKey'](#) to unlock premium function in the Node with from payment service generated 128 Bit Key.

6.8 Page 'Manage Accounts'

Manage Accounts

- Create new USER
- Input: Name
- Delete USER

- Export ADMIN Data
- Export USER Data

> back Home

6.8.1 'Create User'

To create a new user, the APP has to create an USER KEY and send it to node with Cmd 'SetUser'.

6.9 Page 'Setup Sequence / Timer:'

SETUP Sequence / Timer:

New config table 32 entries:

Scene Number

Timer

Duration

Event

Start / Stop

➤ back Setup Home

➤ See Spec. Version 11

Sequence table entries can be read by Cmd ['GetSeqEntry'](#)

Sequence table entries can be written by Cmd ['SetSeqEntry'](#).

Timer entries can be read by Cmd ['GetTimer'](#).

Timer entries can be written by Cmd ['SetTimer'](#).

More info about sequence table, see [Appendix P](#).

More info about Timers, see [Appendix R](#).

7. Descriptions for Touch4Light page (user operating page)

All touches on soft buttons or sliders on the 'Touch4Light' page, will generate an event (ET_BUTTON, ET_SLIDER, etc.), which will be sent into the mesh network (Packet Type 1).

All available Event types are described in [Appendix E](#).

Touch4Light (user page)

Offers all presets per User or admin for selected operation:

Like scene buttons, sliders, color control e.g.

> Back Home

8. Appendixes

The appendixes describe in more detail the software design. Generally there are two software parts in a BRnode:

- The **BRnode firmware** (M-Way) handles the in / out of Bluetooth protocol msg's. It transfers / receives messages via UART interface.
- The **BTnode firmware** (VS) receives/transfers UART msg's and manages input events and luminaires.


8.1 Appendix A: BT communication frame description

An incoming message into the BRnode firmware clarifies if the message belongs to the BRnode xyz.

This follows that the BTnode firmware receives only messages with its unique DestinationID or broadcast messages.

Group	Offset	Size	Field	Value	Description
-	0	1	Sync Byte	0x42 = 66 = ,B‘	Serial sync byte; always 0x42
Header	1	1	Address Length = AL	0xnn	
	2	2	Block Count = BC	0xnnnn	Data Length (DL) is $BC * 8 - PL - 2$
	4	2	Packet Type	0xnnnn	See Appendix F
	6	1	Packet Version	0xnn	
	7	2	Manufacturer	0xnnnn	0 = according open standard 1 = VS
	9	1	CRC Header	0xnn	
Address	10	1	Address Status	0xnn = 0b0f0edcba	Bit field for present Address data (1 = present): a = Source ID field b = Destination ID field c = Destination Type field d = Packet ID field e = Encryption Type field f = Timestamp field
		2	Source ID	0xnnnn	ID of the source node
		2	Destination ID	0xnnnn	ID of destination node
		1	Destination Type	0xnn	0 = Message between BT-/MWAYfirmware 1 = Mesh-Message
		1	Packet ID	0xnn	Necessary to identify response frame
		1	Encryption Type	0xnn	0 = NodekeyID 1 = SystemkeyID N= UserkeyID#N-2; (N=2..251)
		4	Timestamp	0xnnnnnnnn	
		1	CRC Address	0xnn	
Data (encrypted)		1	PL	0xnn	Length of Padding Data
		DL	Data	...	$DL = BC * 8 - PL - 2$
		1	CRC of Data	0xnn	CRC of decrypted Data
		PL	Padding data 0x00	...	Add Padding to reach $DL + PL + 2 = BC * 8$
		1	CRC Data	0xnn	

Group	Offset	Size	Field	Value	Description
		1	CRC of CRCs	0xnn	CRC of CRC Header & CRC Address & CRC Data



8.2 Appendix B: Command description App → MWAYfirmware → VSfirmware

In General:

- If a rxd (uart) message frame fails: it may not possible to select between a command and an event. In this case a simple One-byte-uart response will be delivered with an appropriate MSG_STATUS content.
- All commands need to have the correct amount of parameters since the BT-firmware will check the data command length.
- All commands will be acknowledged with a response frame (Packet ID 3)
- A “scene” in this document is referred as a “Lightlevel” scene where the user may configure color control of a VLT_TYPE_x
- Scene 1 is fallback scene. Will be generated after power on if not exist: brightness: all channels “127”, tim2Target=0
- All virtLums with phys channels configured will output lighlevel using scene 1 after power up.
- Numbers of a virtLum, channel, scene starts with “1” from user perspective. Software intern an array index “0” will be used for “1”
- Step%: For example a brightness slider will transmit a value of 0..254, meaning a % brightness between 0..100%. Other parameters with “step%” act in the same way. For example: The user may see a slider setting of 50% in the APP, while the software transfers step% = 127.
- Time definitions are based on [\(Appendix Q\) \(0..33\)](#).
- In case of more than 1 Byte parameter transfer: We use BIG-ENDIAN Format: For example a 2-byte-transfer with content 64d results in 0040h .
- inputNum: This parameter allows to distinguish between several events of the same type within the reaction tab.
- Any settings in any tab requires a free tab entry. **Overwriting is possible. In this case the VSfirmware will respond with MSG_STATUS_OVERWRITE_WARNING**
- The response of a command leads up with the commandNo, following MsgStatus, following 16-Bit updateLevel (MSB first, LSB second)

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetNodeSystemKey	01	Set a System Key in a BR Node Changes Update Level This command resets all node information and saves the DestinationID in the BTnode firmware	Byte 0..15: System Key Note: SystemKey “0” will reset complete node data (keys, scenes, virtLums, reactionTab etc.)	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key

CommandTypMsg	Cm d/R sp- No	Description	Parameter	Response	Encryption
GetNodeStatus	02	Request Node Status.	None	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p> <p>Byte 4 Status (active=1 / inactive=0): Bit 0: search Bit 1: identify Bit 2: light regulation tasks Bit 3: movement task Bit 4: timestamp valid Byte 5: Node Type (see App. D) Byte 6: Max count physical lums (8 or 64) Byte 7: Count of available physical lums Byte 8: Max count virtual luminaire (4 or 16) Byte 9: Min count virt lum Byte 10: Count ...of virt lum Byte 11: ... of DALI groups Byte 12: ... of virt scenes Byte 13: ... of reaction tab entries Byte 14: ... of inputs (max TabIndex) Byte 15: ... of sequence tab entries Byte 16: ...of timer tab entries Byte 17: Max. reactionTab entries Byte 18: Max. User</p> <p>Response data depends also on Node Status 'Free' or 'Premium'.</p>	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
NodeSearchPhysLum	03	Starts the search for physical (DALI-) Luminaries Changes Update Level	Search Mode: 0 (Clear & Search) 1 (Search only New) 2 (Keep & Search) See also Appendix W	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Generates a broadcast EventMsg "EndOfPhysicalSearch"	System Key
GetNodeUpdateLevel	04	Gets the Update Level of the Node	None	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	System Key / User Key
GetNodePhysLums (Deprecated, see GetNodePhysLums2)	05	Gets the Data of the physical Luminaries	None	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: count of arrays Byte 5..start of Array: Array of Arrays with count of physical Luminaires elements: Pos 0: 2-byte-address Pos 1: 1-byte physical Type (see Appendix J) Pos 2: Status of a <i>PLT_DALI_LED...</i> <i>Bit0: controlGearFailure</i> <i>Bit1: lampFailure</i> <i>Bit2: lampOn</i> <i>Bit3: limitError</i> <i>Bit4: fadeRunning</i> <i>Bit5: resetState</i> <i>Bit6: shortAddress</i> <i>Bit7: powerCycleSeen</i>	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
NodeIdentifyPhysLum	06	Identifies a physical Luminaire	<p>Byte 0/1: Number/address of the physical luminaire: 0x0001..0x0064, 0xFFFF(deviceLED), 0xFFFF (broadcast: all physLums)</p> <p>Byte 2: (0 = Identify Off, 1 = On) Note: Process will turn identify OFF automatically after 1 minute ON</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	System Key
NodeCreateVirtualLum	07	Creates a new virtual Luminaire Changes Update Level	<p>Byte 0: virtual luminaire number (1..16) Byte 1: VLT Type (Appendix H)</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	System Key
GetVirtualLumChannels (maybe obsolete)	08	Reads the luminaire channels of a virtual luminaire num	Byte 0: Number of Virtual Luminaire	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Array of 6 Elements Pos 0: Channel number (0xFF = not used)</p>	System Key

CommandTypMsg	Cm d/R sp- No	Description	Parameter	Response	Encryption
GetNodeVirtualLums (Deprecated, see GetNodeVirtualLums2)	09	Reads all available data of all virtual luminaires which are available	None	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: count of Array Byte 5..max Byte 66 Array of Arrays with count of virtual Luminaires Elements: Pos 0: virtual lum number (1..16) Pos 1: Type, (see Appendix H) Pos 2: Count of channels (which has been set by SetPhysLum-Channel) Pos 3: Status	System Key
GetNodeVirtualLumData (maybe obsolete)	10	Reads the settings of a virtual Luminaire Note: min brightness is calculated from phys drivers “minLevel”. This value is changeable via App.	Byte 0: Number of Virtual Luminaire	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: dimSpeed Byte 5: modeState (Bit7..4: mode, Bit3..0: state) Byte 6: activeBrightness[step%] Byte 7: passivBrightness[step%] Byte 8: basicBrightness[step%] Byte 9: min brightness[step%] Byte 10: time active Byte 11: time passive (see Appendix Q) (0..33)	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetNodeVirtualLumData	11	<p>Writes the settings of a virtual Luminaire</p> <p>Changes Update Level</p> <p>Requires a previous, appropriate NodeCreateVirtualLum SetPhysLumChannel</p> <p>See Appendix U</p>	<p>Byte 0: Number Virtual Luminaire(1..16)</p> <p>Byte 1: dimSpeed (0..255) (700ms units)</p> <p>Byte 2: reserved(internal used)</p> <p>Byte 3: reserved(free)</p> <p>Byte 4: activeBrightness[step%]</p> <p>Byte 5: passiveBrightness[step%]</p> <p>Byte 6: basicBrightness[step%]</p> <p>Byte 7: min brightness[step%]</p> <p>Byte 8: time active</p> <p>Byte 9: time passive</p>	<p>Byte 0: CmdNo</p> <p>Byte 1:MsgStatus (see Appendix I)</p> <p>Byte 2: updateLevel MSB</p> <p>Byte 3: updateLevel LSB</p>	System Key
SetPhysLumChannel	12	<p>Assigns a Virtual Luminaire channel to a Physical Luminaire address/number</p> <p>Changes Update Level</p> <p>Requires a previous NodeSearchPhysLum (if not already done so in the past) and an appropriate NodeCreateVirtualLum</p>	<p>Byte 0: Num virt lum(1..16)</p> <p>Byte 1: virt channel num (1..6)</p> <p>Bit7 =1: resets phys channel (0x81...0x86)</p> <p>Byte 2/3: phys channel address/number (DALI:1..64)</p>	<p>Byte 0: CmdNo</p> <p>Byte 1:MsgStatus (see Appendix I)</p> <p>Byte 2: updateLevel MSB</p> <p>Byte 3: updateLevel LSB</p>	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetNodeScene	13	Sets a scene in Node Changes Update Level	<p>Byte 0: Scene Number(1..64) Note: setting Bit 7 of Byte 0 resets all scene paras (0x81..0xC0)</p> <p>Scene “1” will also be used at PowerOn see Appendix T.</p> <p>Byte 1: Brightness (0..254)</p> <p>Byte 2: Time to Target (Appendix Q) (0..33)</p> <p>Byte 3: Lightlevel channel 1 Byte 4: Lightlevel channel 2 Byte 5: Lightlevel channel 3 Byte 6: Lightlevel channel 4 Byte 7: Lightlevel channel 5 Byte 8: Lightlevel channel 6 (0..254)</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	System Key
GetNodeScene	14	Read a scene from Node	Byte 0: Scene Number(1..64)virtLum2	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: Room brightness[step%] Byte 5: Time to Target (Appendix Q) Byte 6: Lightlevel channel 1 Byte 7: Lightlevel channel 2 Byte 8: Lightlevel channel 3 Byte 9: Lightlevel channel 4 Byte 10: Lightlevel channel 5 Byte 11: Lightlevel channel 6</p>	System Key

CommandTypMsg	Cm d/R sp- No	Description	Parameter	Response	Encryption
GetNodeReactionEntry	15	Reads a Reaction Entry	Byte 0: Number of the Entry (1..250)	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: EventType MSB Byte 5: EventType LSB Byte 6: SourceID MSB Byte 7: SourceID LSB Byte 8: InputNum Byte 9: ActionType Byte 10: UserkeyID (2..251, 255 = all user) Byte 11..17 Para (valid parameter 7 Bytes - depends on ActionType)	System Key
SetNodeReactionEntry	16	Writes a Reaction Entry Changes Update Level Depending on ActionType: Requires a previous, appropriate NodeCreateVirtualLum, SetNodeScene	Byte 0: Number of the entry (1..250) Byte 1: EventType MSB Byte 2: EventType LSB (ET_UNDEF frees tab entry) Byte 3: SourceID MSB Byte 4: SourceID LSB Byte 5: InputNum Byte 6: ActionType Byte 7: UserkeyID (2..251, 255 = all user, 252..254 reserved), Byte 8..xx , depends on ActionType See also Appendix K	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
GetInput	17	Reads complete data of the EventTab	none	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: Entry num x Array of x-Entries Byte 5+x: active (bit oriented) Byte 6+x: enableMesh (bit oriented) Byte 7+x: EventType MSB Byte 8+x: EventType LSB Byte 9+x: max Instance(1..8) Byte 10+x,11+x: see here	System Key
SetInput	18	Writes the data of the Input Changes Update Level	Byte 0/1: EventType Byte 2: active (0,1) Byte 3: enableMesh (0,1) Byte 4: inputNum(0..7) Byte 5,6: Parameter (0xffff will force VSfirmware to set it) See also Appendix E und Appendix K	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	System Key
SetUser	19	Sets a User and its Number. Max.4 users may configure the BRnode. Changes Update Level	Byte 0: Position [0.3] Byte 1: UserKeyID[2..251], [255=reset] Byte 2-17: User crypto key	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB :	System Key
SetLimitKey	20	Transmit payment 128 Bit Key (This is the key for Payment options) Changes Update Level If LimitKey==HiddenKey the premium state will be true	Byte 0: Limit Version (always 0) Byte 1-16: Key (MSB first)	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key

CommandTypMsg	Cm d/R sp- No	Description	Parameter	Response	Encryption
SetHiddenKey (not used any more, since this key will be set during produc- tion phase)	21	Transmit hidden 128 Bit Key (This is the key for Payment op- tions)	Byte 0: Limit Version (always 0) Byte 1-16: Key (MSB first)	Byte 0: CmdNo Byte 1: MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key
GetNodeLimitId	22	Get ID Code from Node	Byte 0: Limit Version (always 0)	Byte 0: CmdNo Byte 1: MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4-19: DeviceLimitKey (MSB first) Byte 20-21: Manufacturer ID	Node Key
TransmitFirmwareData	23	Transmit a new Firmware	Byte 0-3: Firmware Size Byte 4-5: Blocks Total Byte 6-7: Current Block Byte 8-9: Block Size = 256 Byte 10-13: Block Start Address Byte 14-xx: encrypted Block Data Byte xx+2: CRC16 of Byte0..xx	Byte 0: CmdNo Byte 1: MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key
CheckFirmwareData	24	CRC-Check if the received new VSfirmware is valid	None	Byte 0: CmdNo Byte 1: MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key
SwitchToNewFirmware	25	Switch to the new BT firmware	None	Byte 0: CmdNo Byte 1: MsgStatus (see Appendix I) Byte 2: updateLevel MSB=0x00 Byte 3: updateLevel LSB =0x00	Node Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
StartFirmwareUpdate	26	Starts BT firmware update (this mode follows “TransmitFirmwareData”, “CheckFirmwareData”, SwitchToNewFirmware”)	none	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key
NodeDeleteVirtualLum	27	Deletes a virtual Luminaire (and its physLum assignments) Changes Update Level	Byte 0: virtual luminaire number (1..16), 255 → deletes all virtLums	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	System Key
SetLocalTime	28	delivers actual Unix UTC local timestamp upon Request Cmd GetLocalTime	Byte 0-4: local UTC time Byte 0 is LSB	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key
SetNodeID	29	Sets the node ID	Byte 0-1: DestinationID	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	Node Key
GetSeqEntry	30	Gets an entry of the sequence table	Byte 0: entry number (1..64)	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: Scene number Byte 5: Pause time Byte 6: Next entry See <i>SetSeqEntry</i>	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetSeqEntry	31	<p>Sets an entry in the sequence table</p> <p>Changes Update Level</p> <p>Note: A sequence table entry should be free and a scene number must be configured via “SetNodeScene” prior, otherwise warning/error. See also Appendix P</p>	<p>Byte 0: Entry number [1..64] Note: setting Bit 7 of Byte 0 resets entry. Byte 1: Scene number (1..64) Byte 2: Pause time (0..33) Byte 3: Bit 7: Event bit, 1=send Bit 6..0: Next Entry (1..64, 0x7e=stop)</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	System Key
SetColorControl	32	<p>Feedback function: Sets the current light levels and brightness for a virt lum num (for a new BR App slider position) and activates the current light channels (shows the light).</p> <p>Requires a previous, appropriate NodeCreateVirtualLum, SetPhysLumChannel</p>	<p>Byte 0: Virt lum num (1..16) Byte 1: brightness (0..254) Byte 2: Lightlevel channel 1 Byte 3: Lightlevel channel 2 Byte 4: Lightlevel channel 3 Byte 5: Lightlevel channel 4 Byte 6: Lightlevel channel 5 Byte 7: Lightlevel channel 6 (0..254)</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	System Key (bei Systemkonfiguration) <u>oder</u> User-Key (bei Touch4Light Oberfläche)
GetTimer	33	Get a timer in the Node	Byte 0: Timer Number (1..32)	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: Timer Num Byte5-8: timestamp target Byte 9: controlField</p>	System Key

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetTimer	34	Set a timer in the Node Changes Update Level	Byte 0: Timer Number (1..32) Byte 1-4: initial timestamp target Byte 5: Weekday Field (Bit 0=Mon, Bit 1=Tuesday etc.) Byte 6: Control Field (0xFF resets entry) Bit0: daily Bit1: weekly Bit2: monthly Bit3: yearly (if Bit0-3=0, no repetition, just one event) Bit4: send event to mesh Bit5: enable=1/disable=0	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	System Key
SendRawData	35	Send raw data to interface (ex. DALI) for debug purposes (Tester)	Byte 0-7: raw data See Appendix Z	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: driver response data	Node Key
GetVirtLumLevel	36	Reads the actual brightness and channel levels of a virtual Luminaire. This command maybe helpful for slider sync	Byte 0: Num of Virtual Luminaire	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: brightness[step%][0..254] Byte 5..10: channel1..6 [0..254]	SystemKey / UserKey

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetScene2VirtLum	37	<p>Sets channel values of a scene to a virtual Luminaire</p> <p>Changes Update Level</p> <p>Requires a previous, appropriate NodeCreateVirtualLum, SetPhysLumChannel, SetNodeScene</p>	<p>Byte 0: Num of Virtual Luminaire(1..16), (0xFF = all available virtLums)</p> <p>Byte 1: Num of scene(1..64)</p>	<p>Byte 0: CmdNo</p> <p>Byte 1:MsgStatus (see Appendix I)</p> <p>Byte 2: updateLevel MSB</p> <p>Byte 3: updateLevel LSB</p>	SystemKey
GetSensorData	38	Get actual data from sensor (movement & brightness).	none	<p>Byte 0: CmdNo</p> <p>Byte 1:MsgStatus (see Appendix I)</p> <p>Byte 2: updateLevel MSB</p> <p>Byte 3: updateLevel LSB</p> <p>Byte 4: Movement State</p> <p>Or if CONNECT:</p> <p>Bit 1: Button 1 pressed</p> <p>Bit 2: Button 2 pressed</p> <p>Or if CONNECT_PLUS:</p> <p>Bit 1: Button 1 pressed</p> <p>Bit 2: Button 2 pressed</p> <p>Bit 3: Button 3 pressed</p> <p>Bit 4: Button 4 pressed</p> <p>Byte 5..6: Brightness value</p>	SystemKey
GetNewSearchData	39	<p>Delivers info about newly found phys lum channels after a search (see Appendix W)</p>	none	<p>Byte 0: CmdNo</p> <p>Byte 1:MsgStatus (see Appendix I)</p> <p>Byte 2: updateLevel MSB</p> <p>Byte 3: updateLevel LSB</p> <p>Byte 4 (MSB) .. Byte 11 (LSB)</p> <p>(Each bit declares phys lum channel whereare Byte 8, Bit0 defines physLum channel address “1” and Byte 1, Bit 7 defines physLum channel address “64”</p>	SystemKey

CommandTypMsg	Cm d/R sp- No	Description	Parameter	Response	Encryption
Debug	40	<p>Allows to set an Event. Allows to turn on/off Debug outputs</p> <p>Note: An “Debug eventType” command will not</p> <ul style="list-style-type: none"> • Check destinationID, • Check sourceID, • Check user • Send Event to Mesh • Send an EventStatus 	<p>Byte 0: type of debug command 1: debug output, 2: set Event 3: re-program DALI-Groups</p> <p>if Byte 0==1 then Parameter Byte 1: 0=off, >0=on</p> <p>if Byte 0==2 then Param Byte 1: eventType Param Byte 2-10: event-param1-8</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	NodeKey
GetVersion	41	Delivers Application-, Bootloader- and Hardware-Version	none	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: Firmware major version Byte 5: Firmware minor version Byte 6: Bootloader major vers. Byte 7: Bootloader minor vers. Byte 8: Hardware major vers. Byte 9: Hardware minor vers.</p>	SystemKey
SetBrightnessRef	42	<p>Sets a reference control value for light regulation. Stops and starts light regulation depending on parameter</p>	<p>Byte 0: reference MSB Byte 1: reference LSB</p> <p>Note: 0xFFFF: stops light regulation 0xFFFE: takes mean sensor reading 0..9999: takes user ref value</p>	<p>Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB</p>	SystemKey

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
CheckFirmwareCompatibility	43	„updatePackage“-Handling für unterschiedliche nodeDevice Komponenten. Für eine Komponente von FirmwareType „1“ werden nur bestimmte nodeDeviceTypen aktualisiert.	Byte 0: 0 Byte 1: 0 Byte 2: minor version Byte 3: major version Byte 4: FirmwareType / ComponentID	Byte 0: CmdNo Byte 1:MsgStatus Byte 2: updateLevel MSB Byte 3: updateLevel LSB <i>Wenn Response CMD_UNKOWN hat das node-Device noch einen älteren Softwarestand und es kann direkt mit „StartFirmwareUpdate“ fortgefahren werden.</i> <i>Wenn Response WRONG_DESTINATION ist das updatePackage nicht für das nodeDevice gedacht. Ein folgendes „StartFirmwareUpdate“ wird gleichermaßen abgewiesen.</i>	Node Key
ConfigMoveSendInterval	44	Configures how often a detected movement signal should be send into mesh	Byte 0: 1..255 1=1*700ms 2=2*700ms .. 255=255*700ms=ca.3min	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	NodeKey
Reserved for future use	45				
Reserved for future use	46				

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
SetNodeReactionEntryNoConstraints	47	This is an adaption of SetNodeReactionEntry command, but: Allows reactionTab settings although physDev, scene, timer, sequences etc. may not available by the time SetNodeReactionEntryNoConstraints has been received. If not available a warning MSG_STATUS_IGNORE_SET_REACTION_CONSTRAINTS will be delivered.	Same as <i>SetNodeReactionEntry</i>	Same as <i>SetNodeReactionEntry</i>	SystemKey
GetNodeVirtualLums2	48	Same as GetNodeVirtualLums in addition actual light level.	None	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: count of Array Byte 5..start of array's: Array: Pos 0: virtual lum number(1..16) Pos 1: Type, (see Appendix H) Pos 2: Count of channels (which has been set by SetPhysLum-Channel) Pos 3: Status Pos 4: actual light level	SystemKey
GetBrightnessSensorRef	49	Retrieves the sensor brightness reference for light regulation (which is enclosed in "eventTab.parameter")	None	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: ref MSB Byte 5: ref LSB	SystemKey

CommandTypMsg	Cmd/Rsp-No	Description	Parameter	Response	Encryption
GetNodePhysLums2	50	Gets the Data of the physical Luminaries with reduced response data	None	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: count of arrays Byte 5..max Byte 197: Array of Arrays with count of physical Luminaires elements: Pos 0: 1-byte-address Pos 1: 1-byte physical Type (see Appendix J)	System Key
SetTabletId	51	Sets tablet ID for copy / paste APP-configuration. Used by App only	Byte 0: MSB Id Byte 1: LSB Id	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB	NodeKey
GetTabletId	52	Gets tablet ID for copy / paste APP-configuration. Used by App only	none	Byte 0: CmdNo Byte 1:MsgStatus (see Appendix I) Byte 2: updateLevel MSB Byte 3: updateLevel LSB Byte 4: MSB Id Byte 5: LSB Id	NodeKey

A BTresponse upon a BTcmd will use the BT communication frame with Packet ID 3

8.3 Appendix C: Reaction List description

Incoming BT-Event messages will be handled internally in the BTnode software with a reaction tab. The tab need to be setup via BTcommand “SetNodeReactionEntry” for each desired action. Each action is represented by one tab entry. Max. 250 entries are possible.

Structure of one entry in a reaction tab[max.250]

Name	Description	Byte count
Event Type (see Appendix E)	The type of an input (Brightness / Movement / Button / Lightlevel / etc.)	2
Event SourceID	SourceID	2
Event inputNum	inputNum (each input in the node has its own inputNum)	1
Action Type	Defines the reaction of a BTeven	1
User number	Defines the accessibility of the reaction (0xFF == free access)	1
Parameter	depends on Action Type (see AT_Parameter)	1 to 6

ActionType

```
#define AT_UNDEF (0)
```

```
#define AT_LIGHT_SCENE (1)
```

Outputs a lightlevel to the specified virtLum type channels. Lightlevel will be retrieved from the scene channels. Scene channels which are defined but not matched with virtLum type will be ignored.

If mode=auto: the incoming event will be used as a “time button” – which means light control is active (this is only possible, if a time active/passive has been configured for the system luminaire). Light regulation is active as long active time has been expired.

If mode>manual: light control and light regulation will be rejected if processed.

```
#define AT_DIM_UP_DOWN_BRIGHTNESS (2)
```

Each event outputs a lightlevel: The brightness will change over “stepCount %” while the color schema is fix according the specified scene.

```
#define AT_DIM_UP_DOWN_COLOR (3)
```

Based on the mean brightness value of both scenes: Each event outputs a lightlevel of “stepCount lightlevel” for the specified color channels in the *channelSelector* byte. Non specified channels in *channelSelector* outputs a fix mean channel lightlevel of both scene channel level.


```
#define AT_LIGHT_CONTROL (4)
```

A virtLum in manual mode forces a lightlevel change by an user action. An automatic mode triggers a lightlevel change by a timer or sensor. The mode change can be configured with e.g. an EV_BT_BUTTON or a "Touch for Light button" on the HandyApp.

```
#define AT_TIMER (5) //obsolete
```

```
#define AT_EVENT_TAB_MANIP (6)
```

Allows a parameter change in the eventType structure. See [Appendix C](#)

```
#define AT_SEQUENCE_PROCESS (7)
```

See [Appendix P](#)

```
#define AT_LIGHT_REGULATION (8)
```

Internal use in VSfirmware: takes action on FG due to an external light regulation

```
#define AT_SLIDER_CONTROL (9)
```

If ET_SLIDER_CONTROL: Sets channels of a virtLum directly, if ET_SLIDER a slider type will be used (channel calulations by VSfirmware)

```
#define AT_BEACON_STATE (10)
```

An event (e.g. ET_BT_BUTTON_TYPE_x) can switch indirectly Beacon function On/Off/Toggle by sending appropriate message VSfirmware → MWAYfirmware

Action Types with Parameter Field

ActionTyp	num Para	Parameter 1	Param 2	Param 3	Param 4
AT_LIGHT_SCENE	4	Virt. Lum No[1..16]	Scene No[1..64]	Not used	Mode Manual = 0, Auto = 1
AT_DIM_UP_DOWN_BRIG HTNESS	4	Virt. Lum No[1..16]	Up[1] / Down[0]	Scene No[1..64]	StepCount [0..255]
AT_DIM_UP_DOWN_COL OR	4	Virt. Lum No[1..16]	ChannelSelect (bit: d0CC CCCC) Bits "C" Selects channels Bit d=1 DIMM UP Bit d=0 DIMM DOWN	To Scene [1..64]	StepCount [0..255]

AT_LIGHT_CONTROL	4	Virt. Lum No[1..16]	changeLL (activeLL, passiveLL, basicLL) Description: changes actualLL to "changeLL"	moveSenseAct (Appendix V)	Scene No[1..64]
AT_EVENT_MANIP	4	Event Type	sensorActive(low half byte) enableMesh(high half byte) for each half byte: Disable = 0 Enable = 1 Toggle=2 Keep=4	Value	Value
AT_SEQUENCE_PROCESS	2	Virt. Lum No[1..16]	startEntry(1..64, 0x7E=stop, 0xFE=stop & enableEvent)		
AT_LIGHT_REGULATION	2	Virt. Lum No[1..16]	Scene[1..64]		
AT_SLIDER_CONTROL (1)	3	Virt. Lum No[1..16]	slider type (see Appendix X)	Scene[1..64]	
AT_BEACON_STATE (2)	1	State (Off=0, On=1,Toggle=2)			

Notes:

- (1) A reaction of ET_SLIDER with AT_SLIDER_CONTROL acts on a FunctionalGroup which owns a scene number itself. A scene number is therefore not necessary in the App for now, but needs to be delivered for message length. A scene number may be used in the future in conjunction with ET_SLIDER_CONTROL i.g. configuration of a scene...
- (2) The action AT_BEACON_STATE sends SetBeaconState, see [Appendix L](#)

8.4 Appendix D: List of Node Types

NodeType	#define	FirmwareID	HW-Input	Sensor	Dali	Comment
UNDEF	0	-	-	-	-	
MULTISENSOR_XS	1	1	0	Movement, Brightness	yes	
CONNECT	2	1	2	-	-	Connection of 2 HW-switches
MULTISENSOR_XL	3	1	2	Movement, Brightness	yes	sensor range bigger
CONNECT_ME	4	1	0	-	yes	
E27	5	2	0	-	-	
E27_RING	6	2	0	-	-	
DIGI_LED_BLU	7	tbd	0	-	yes	4-channel-driver with bluetooth
CONNECT_PB4	8	1	4	-	-	Connection of 4 HW-switches

8.5 Appendix E: Event (Input) Types

//possible Node events for all type of known deviceNodes

#define ET_UNDEF	(0)	//undefined
#define ET_BT_BUTTON_TYPE_1	(1)	//a bluetooth button with four wipes to be learned in by App
#define ET_BT_BUTTON_TYPE_2	(2)	//a bluetooth button with four wipes to be learned in by App
#define ET_BT_BUTTON_TYPE_3	(3)	//a bluetooth button with four wipes to be learned in by App
#define ET_BT_BUTTON_TYPE_4	(4)	//a bluetooth button with four wipes to be learned in by App
#define ET_BUTTON	(5)	//AppEvent, push button
#define ET_SENSE_MOVEMENT	(6)	//movement sensor
#define ET_SENSE_BRIGHTNESS	(7)	//brightness sensor
#define ET_LIGHT_LEVEL	(8)	//used for reactionTab to define FunctionalGroups which belongs to light regulation
#define ET_SLIDER	(9)	//AppEvent, sets channel(s) according slider position
#define ET_TIMER	(10)	//internal VS event to start time controlled action
#define ET_REGULATION	(11)	//event to adjust light output for an external light regulation
#define ET_SLIDER_CONTROL	(12)	//AppEvent, event reflects SetColorControl
#define ET_EXT_BEACON	(13)	
#define ET_IO_BUTTON	(14)	//for NT_VS_CONNECT
#define ET_SEQUENCE	(15)	//internal VS event to start an action upon "end of a sequence"

//eventType's used from BT to BR firmware

#define ET_CHANGE_SEQUENCE (253)

#define ET_POWER_READY (254)

#define ET_END_OF_PHYS_SEARCH (255)

To react on its own input events, an appropriate entry in the reaction tab is needed via the “Bluerange” BR App

Structure of one entry in an Event Tab[num of inputs]

Name	Description	Byte count
inputActive	An inputNum0..7 can be bitwise(0..7) enabled=1 / disabled=0 configurable via AT_EVENT_MANIP BTevent msg	1 (default=0)
enableMesh	Once inputActive and enableMesh are enabled, an event registration can be broadcast thru the BT mesh network configurable via AT_EVENT_MANIP BTevent msg	1 (default=0)
eventType	Button or Brightness or Movement or Lightlevel or...	2
Parameter	Reserved	2

The event tab length is fixed for a BRnode (node) type and reflects the “Count of available Inputs” of a BRnode.

- **Following EventMsgs with PacketType=PT_EVENT exist.**
- **Encryption type is UserKey if send from HandyApp, otherwise SystemKey**
- **All EventMsgs will be acknowledged just with one UART byte directly.** It will be delivered after the availability of settings has been checked but before the execution of the action will be fulfilled.
- **Sending Events from HandyApp must use an (user) encryption type >= 2 in address field of the BT msg. This implements also a correct user number (0xFF == all users) in the reactionTab.**
- **Sending Events not from HandyApp must use system encryption type = 1 in address field of the BT msg. This implements also a correct user number = 0xff in the reactionTab.**

EventMsg	Event No.	Description	Parameter	UART-Response
Button	ET_BUTTON	A smartphone / tablet Button-Event. Sends a button press / hold / release If “press” → event time is 0 If “hold” → event time is xx and defines a dimming request If “release” → event time is xx	Byte 0: input-Num(0..255) Byte 1: press(1), release(2), hold(3)	Byte 0: MsgStatus

EventMsg	Event No.	Description	Parameter	UART-Response
ButtonBT	ET_BT_BUTTON_TYPE[1..4]	A Bluetooth-Button Event. Sends a button press / hold / release If “press” → event time is 0 If “hold” → event time is xx and defines a dimming request If “release” → event time is xx	Byte 0: inputNum(0..4) Byte 1: press(1), release(2), hold(3)	Byte 0: MsgStatus
Slider	ET_SLIDER	A smartphone / tablet Slider-Event. Sends a new slider position to a slider type	Byte 0: inputNum Byte 1: position Byte 2: control: 0=normal, 1=LR Stellglied	Byte 0: MsgStatus
SliderControl	ET_SLIDER_CONTROL	A smartphone / tablet Slider-Event without LLscene processing. Sends a new channel setting to a virtLum	Byte 0: inputNum Byte 1: brightness (0..254) Byte 2: channel 1(R) Byte 3: channel 2(G) Byte 4: channel 3(B) Byte 5: channel 4(W) Byte 6: channel 5(A) Byte 7: channel 6(F) (0..254)	Byte 0: MsgStatus
SystemTime (unused for now)	ET_SYSTEM_TIME	Sends the BRnode node system time (unused for now)	Byte 0: inputNum Byte 1-4: sysTime (MSB first)	Byte 0: MsgStatus
Movement	ET_SENSE_MOVEMENT	Sends a movement sensor status	Byte 0: inputNum Byte 1: 1=new Event if timer interval elapsed 1+C=“C” counts detected within timer interval Timer interval: default = 11, which is 11*770ms See also Config-MoveSendInterval	Byte 0: MsgStatus

EventMsg	Event No.	Description	Parameter	UART-Response
Brightness	ET_SENSE_BRIGHTNESS	Sends a brightness sensor info (every 8 sec)	Byte 0: inputNum Byte 1/2: current-BrightnessValue Byte 3/4: targetBrightnessValue	Byte 0: MsgStatus
LightLevel	ET_LIGHT_LEVEL	<i>VSfirmware only: Defines which virtLums belongs to own active light regulation within reaction tab</i>		
Timer	ET_TIMER	Event to trigger a time controlled action	Byte 0: TimerNum(1.32)	Byte 0: MsgStatus
Regulation	ET_REGULATION	<i>VSfirmware only: Defines which virtLums belongs to external light regulation within reaction tab. Receiving this event forces those virtLums to change its light level via DAPC independent of byte1. Additional control is possible via "control" byte1.</i>	Byte 0: DAPC [0..254] Byte 1: control[0,1]: 0= set DAPC only 1= init Auto active	Byte 0: MsgStatus
ExtBeacon	ET_EXT_BEACON	This event will be sent by BR firmware if an external matching Beacon is recognised	Byte 0: inputNum(== Beacon ID)	
IO_Button	ET_IO_BUTTON	The I/O-Inputs of a Connect device sends this event for button press / hold / release. If "press" → event time is 0 If "hold" → event time is xx and defines a dimming request If "release" → event time is xx	Byte 0: inputNum(0..1) 0 = Input 1, 1 = Input 2 Byte 1: press(1), release(2), hold(3)	Byte 0: MsgStatus
PowerReady	ET_POWER_READY	<i>a)This Event can be sent by the MWAYfirmware as request. b)Send by VSfirmware as soon the μC voltage has been stabilized or as a response upon a request. After receiving this Event by the MWAYfirmware, it can start its Bluetooth process.</i>	Byte 0: (1 ready, 0 not ready)	
EndOfSequence	ET_SEQUENCE	Generated by VS at the end of a sequence, if reactionTab set accordingly.	Byte 0: inputNum = SeqNum(tbd)	

EventMsg	Event No.	Description	Parameter	UART-Response
EndOfPhysicalSearch	ET_END_OF_PHYS_SEARCH	Upon a BTCmd "NodeSearchPhysLum" this BTEvent msg will send by BT firmware if the search of physical luminaire ends up.	Byte 0-8: all available physical luminaire addresses, MSB first. Setting/Resetting of Bit63..Bit0 indicates address 64..1 found(=1) / not found(=0)	

The following table lists available EventType for **NT_VS_MULTISENSOR_EM_E** and can be used to set reactionTab appropriate regarding sourceID, inputNum and user:

EcentType	enclosed in eventTab for NT_VS_MULTISENSOR_EM_E	intern source events	extern Events (not from extern node)	BTfirmware check within ReactionTab			AppEvent	ManualEvent
				sourceID	inputNum	user		
ET_BT_BUTTON_TYPE_1	x		x	y	y	n		x
ET_BT_BUTTON_TYPE_2	x		x	y	y	n		x
ET_BT_BUTTON_TYPE_3	x		x	y	y	n		x
ET_BT_BUTTON_TYPE_4	x		x	y	y	n		x
ET_SENSE_MOVEMENT	x	x		y	n	n		
ET_SENSE_BRIGHTNESS	x	x		y	n	n		
ET_LIGHT_LEVEL	x	x		y	n	n		
ET_SYSTEM_TIME_INFO	x			y	n	n		
ET_REGULATION	x	x		y	n	n		
ET_EXT_BEACON	x		x	y	y	n		
ET_BUTTON			x	n	y	y	x	x
ET_SLIDER			x	n	y	y	x	x
ET_SLIDER_CONTROL			x	n	y	y	x	x

#define ET_IO_BUTTON 30 is used for node type NT_BLUE RANGE_CONNECT

Special Events, not listed in EventTab

VSfirmware → MWAYfirmware:

#define ET_CHANGE_SCENE

#define ET_END_OF_PHYS_SEARCH

0x00FD //as a notice for "nextEntry" (or "finished") in scene sequence

0x00FF

VSfirmware ↔ MWAYfirmware:
#define ET_POWER_READY

0x00FE //as request from MWAYfirmware / as a power ready state from VSfirmware

8.6 Appendix F: List of Packet- and Destination-Types in MsgHeader

PacketType		description
PT_UNDEF	0	undefined
PT_EVENT	1	Event
PT_CMD	2	Command
PT_RSP	3	Response

The PacketType defines the overall content in the Data-Block of the communication frame. ([Appendix A](#)).

For PacketType 2 and 3, the content is listed in [Appendix B](#), for each command.

For PacketType 1, see [Appendix C](#).

DestinationType		description
DT_TYPE_LOCAL	0	Internally generated events which also processed on the same node Received events from node coupled devices (e.g. BT_BUTTON_TYPE_X)
DT_TYPE_MESH	1	Received commands / events from mesh Sending commands / events into mesh

8.7 Appendix G: Definition of User Dataset (for User 2D Code Preparation)

The dataset for the User 2D Code includes the following information:

- Mesh Name
- User number
- User Key
- GATT Key
- Update Level
- List of Nodes which the User can connect to

Will be extended in cooperation with M-Way, if necessary!

8.8 Appendix H: Definition of the System Luminaire Types

Virtual LumType		description
VLT_AVAILABLE_FOR_THIS_TYPE	0	an intern BT firmware value. Some or all channels may be available
VLT_SINGLE_LUMINAIRE	1	fix 1-channel luminaire (a channel 0 config only, all other will result in an error)
VLT_TUNEABLE_WHITE_LUMINAIRE	2	fix 2 channel luminaire (a channel 0,1 config only, all other will result in an error)
VLT_RGB_LUMINAIRE	3	fix 3 channel luminaire (a channel 0,1,2 config only, all other will result in an error)
VLT_RGBW_LUMINAIRE	4	fix 4 channel luminaire (a channel 0,1,2,3 config only, all other will result in an error)
VLT_RGBWA_LUMINAIRE	5	fix 5 channel luminaire (a channel 0,1,2,3,4 config only, a config on channel 5 will result in an error)
VLT_RGBWAF_LUMINAIRE	6	fix 6 channel luminaire (a full channel 0,1,2,3,4,5 configuration required)
VLT_UNAVAILABLE	255	an intern BT firmware value. Some channels may be unavailable

8.9 Appendix I: Msg_Status

The **MsgStatus** will be sent in a **BTresponse msg** from the **BTnode software module** upon receiving a correct encrypted **BTcommand msg** from the **BRnode software module**.

A BTresponse or an UART-Response upon an extern Event may have one of the following status codes:

```
//Errors
#define MSG_STATUS_OK 0x00 //no problems has been detected
#define MSG_STATUS_WRONG_DATALENGTH 0x01 //The data length of command / event dissatisfies
#define MSG_STATUS_NOT_ACCEPTED_DURING_SEARCH 0x02 //a command has been received while searching physical luminaire channels
#define MSG_STATUS_NO_FREE_VIRT_LUM_CHANNEL 0x03 //a virtLum type could not be created
#define MSG_STATUS_UNAVAILABLE_VIRT_LUM_NUM 0x04 //a luminaire number of a command para doesn't exist
//an reaction func detects missing luminaire number
#define MSG_STATUS_INVALID_PHYS_LUM_ADDR 0x05 //used in CMD_NODE_IDENTIFY_PHYS_LUM
#define MSG_STATUS_PHYS_LUM_NUM_NOT_DETECTED 0x06 //a virtLum channel can be used only if the channel group address exist
#define MSG_STATUS_SCENE_NOT_AVAILABLE 0x07 //the command or the Re-action cannot be placed: missing lightLevelScene num
#define MSG_STATUS_CHANNEL_NOT_FREE 0x09 //not used anymore / for now
#define MSG_STATUS_REACTION_ENTRY_NOT_AVAILABLE 0x09 //intern SW error of VSfirmware
#define MSG_STATUS_ACTION_TYPE_NOT_AVAILABLE 0x0a //the command SetNodeReactionEntry failed
#define MSG_STATUS_WRONG_EVENT_TYPE 0x0b //the command SetNodeReactionEntry failed
#define MSG_STATUS_TIME_EXCEEDS 0x0c //wrong parameter in SetNodeScene
#define MSG_STATUS_GROUP_CREATION_FAILED 0x0d //the command SetPhysLumChannel failed
#define MSG_STATUS_CHANNEL_LIMIT_ERROR 0x0e //creating a group address > 16 failed
#define MSG_STATUS_VIRT_LUM_TYPE_CHANNEL_UNAVAILABLE 0x0f //creating a virtLum type failed: not enough group addresses
#define MSG_STATUS_NO_SENSOR_AVAILABLE 0x10 //the type of the nodeDevice does not have any sensor connected
#define MSG_STATUS_WRONG_VIRT_LUM_INDEX 0x11 //A reaction could not be placed
#define MSG_STATUS_WRONG_SCENE_INDEX 0x12 //A reaction could not be placed
#define MSG_STATUS_WRONG_SEQUENCE_INDEX 0x13 //A reaction could not be placed
#define MSG_STATUS_CMD_REQUIRES_SYSTEM_KEY 0x14 //the command has wrong encryption key
```

```

#define MSG_STATUS_CMD_REQUIRES_NODE_KEY      0x15 //the command has wrong encryption key
#define MSG_STATUS_CMD_UNKOWN                  0x16 //wrong cmdID received

#define MSG_STATUS_RXD_DATA_CRC_ERR            0x17 //the message receiver detects an error
#define MSG_STATUS_RXD_HEADER_CRC_ERR          0x18 //the message receiver detects an error
#define MSG_STATUS_RXD_MAX_LENGTH_ERR          0x19 //the message receiver detects an error
#define MSG_STATUS_RXD_LESS_DATA_ERR           0x1a //the message receiver detects an error
#define MSG_STATUS_RXD_ADDR_CRC_ERR            0x1b //the message receiver detects an error
#define MSG_STATUS_RXD_TOTAL_CRC_ERR           0x1c //the message receiver detects an error
#define MSG_STATUS_RXD_FRAME_ERR               0x1d //the message receiver detects an error
#define MSG_STATUS_RXD_HEADER_ADDRESS_LENGTH0x1e //the message receiver detects an error
#define MSG_STATUS_RXD_PACKET_ID_ERR           0x1f //the message receiver detects an error
#define MSG_STATUS_GROUP_ADDR_REJECTION_FAILED 0x20 //verification of removing addr within group failed
#define MSG_STATUS_UPDATE_NOT_STARTED          0x21 //TransmitFirmwareData failed
#define MSG_STATUS_FIRMWARE_INCOMPLETE         0x22 //CheckFirmwareData failed
#define MSG_STATUS_CHECKSUM_NOT_OK             0x23 //CheckFirmwareData failed
#define MSG_STATUS_USER_NOT_AVAILABLE          0x24 //SetNodeReactionEntry failed or reactionTab has no appropriate user entry
#define MSG_STATUS_EVENT_NOT_ACTIVATED         0x25 //Event not activated in inputEventTab
#define MSG_STATUS_WRONG_DESTINATION           0x26 //Event could not be proceeded
#define MSG_STATUS_EVENT_NOT_USED              0x27 //An extern Event has been received which cannot be used here
#define MSG_STATUS_SOURCE_ID_DOESNT_MATCH      0x28 //the sourceID in reactionTab for the extern Event doesn't match
#define MSG_STATUS_INPUT_NUM_DOESNT_MATCH      0x29 //inputNum of Event doesn't match with reactionTab
#define MSG_STATUS_DRIVER_TYPE_NOT_AVAILABLE  0x2a //SendRawData failed
#define MSG_STATUS_DRIVER_NO_ANSWER            0x2b //SendRawData failed
#define MSG_STATUS_WRONG_CMD_PARA              0x2c //at least one parameter was wrong
#define MSG_STATUS_WRONG_CMD_PARA1            0x2d //para1 exceeds
#define MSG_STATUS_WRONG_CMD_PARA2            0x2e //para2 exceeds
#define MSG_STATUS_WRONG_CMD_PARA3            0x2f //para3 exceeds
#define MSG_STATUS_WRONG_CMD_PARA4            0x30 //para4 exceeds
#define MSG_STATUS_WRONG_CMD_PARA5            0x31 //para5 exceeds
#define MSG_STATUS_UPDATE_NOT_AVAILABLE_ERR    0x32 //could not resolve any of the Download-Commands
#define MSG_STATUS_INCOMPATIBEL_VIRT_LUM       0x33 //"DT8" <--> "normal" Addr not convenient to virtLum
#define MSG_STATUS_EVENT_TAB_ERR               0x34 //Event could not be found in eventTab
#define MSG_STATUS_RXD_DATA_ENCRYPTED_CRC_ERR   0x35 //CRC of encrypted data failed
#define MSG_STATUS_BLOCK_NUMBER_INVALID        0x36 //invalid block num
#define MSG_STATUS_BLOCKSIZE_NOT_OK            0x37 //blocksize not ok
#define MSG_STATUS_BLOCKSTARTADDR_NOT_ZERO     0x38 //blockStartAddress must be zero according definition
#define MSG_STATUS_RXD_PACKET_ERR              0x39 //datLength too big, wrong packet
#define MSG_STATUS_LIMIT_REACHED               0x40 //limit either of virtLum or physLum count exceeds
#define MSG_STATUS_DECRYPTION_FAILED           0x41 //decryption Key 0 or matching failed
#define MSG_STATUS_WRONG_USER_KEY_ID           0x42 //SetUser failed
#define MSG_STATUS_WRONG_NODE_TYPE             0x43 //Not supported by this node type
#define MSG_STATUS_LOCAL_TIME_INVALID          0x44 //missing local time
#define MSG_STATUS_RSP_DATA_OUT_LENGTH_EXCEEDS 0x45 //response data too big for fruity mesh 0.7.1400

//Warnings / Infos
#define MSG_STATUS_IGNORE_SET_REACTION_CONSTRAINTS (0xe0) //informs about reactionTab settings although physDev, scene, timer, sequences
//etc. may not available by the time SetNodeReactionEntry has been received
#define MSG_STATUS_OVERWRITE_INFO              0xe1 //Overwrite info of any tab settings / phys lum addresses
#define MSG_STATUS_FIRMWARE_RECEIVED_INFO      0xe2 //firmware update completed
#define MSG_STATUS_LUMINAIRE_INCOMPATIBEL_SCENE 0xe3 //Output of a luminaire channel failed: scene channel not configured

```

```
#define MSG_STATUS_MISSING_CONDITION  
#define MSG_STATUS_LR_ACTIVE
```

```
0xe4 //Command could not be performed, missing condition  
0xe5 //Command could be performed, while light regulation active
```

8.10 Appendix J: Physical luminaire type feature

```
#define TYPE_FEATURE_NORMAL (0) //App-Anzeige "normal"  
#define TYPE_FEATURE_DT8_Tc (1) //App-Anzeige "DT8-Tc"  
#define TYPE_FEATURE_DT8_XY (2) //App-Anzeige "DT8-X/Y"
```

8.11 Appendix K: Possible EventType / ActionType Combinations

	AT_LIGHT_SCENE	AT_DIM_UP_DOWN_X	AT_LIGHT_CONTROL	AT_TIMER	AT_EVENT_TAB_MANIP	AT_SEQUENCE_PROCESS	AT_LIGHT_REGULATION	AT_SLIDER_CONTROL	AT_BEACON_STATE
ET_BUTTON (App)	x	x		x		x	x		x
ET_BT_BUTTON_TYPE_x	x	x		x	x	x			x
ET_SLIDER (App)							x	x	
ET_SLIDER_CONTROL (App)								x	
ET_SENSE_MOVEMENT	x		x	x		x			
ET_SENSE_BRIGHTNESS									
ET_LIGHT_LEVEL							x		
ET_SYSTEM_TIME									
ET_TIMER	x					x			
ET_REGULATION							x		
ET_EXT_BEACON									x
ET_SEQUENCE	x					x			

AT_LIGHT_SCENE	Outputs a "Lightlevel"Scene to a virtLum
AT_DIM_UP_DOWN_X	outputs one dimm step of brightness of a "Lightlevel"Scene
AT_LIGHT_CONTROL	acts on a virtLum regarding activeLL, passiveLL, basicLL: changes brightness of a "Lightlevel"Scene
AT_TIMER	enable / disable timerNo in timerTab
AT_EVENT_TAB_MANIP	sets / resets activation and/or event forwarding into mesh of a none App event
AT_SEQUENCE_PROCESS	(re-)starts a sequence process of "Lightlevel"Scenes
AT_LIGHT_REGULATION	defines which virtLum belongs to a light regulation
AT_SLIDER_CONTROL	if ET_SLIDER_CONTROL: sets complete channels of a virtLum type independent of its "lightlevel"Scene"; if ET_SLIDER: sets a specific channel according to slider position, needs a "Lightlevel"Scene
AT_BEACON_STATE	if ET_EXT_BEACON: sends a SEND_CMD_BEACON_STATE command to Brfirmware; If any BUTTON: changes state

ET_BUTTON (App)	Event delivered from App. Has no entry in eventTab. Has no specific sourceID. Needs user rights
ET_BT_BUTTON_TYPE_x	Event received by BRfirmware forwarded to BTfirmware. Has entry in eventTab. Has specific sourceID. Needs user rights.
ET_SLIDER (App)	Event delivered from App with a slider position. Has no entry in eventTab. Has no specific sourceID. Needs user rights
ET_SLIDER_CONTROL (App)	Event delivered from App with all virtLum type channel values. Has no entry in eventTab. Has no specific sourceID. Needs user rights
ET_SENSE_MOVEMENT	Event is generated from own Node and processed. Does nothing if event comes from external Node.
ET_SENSE_BRIGHTNESS	Event is generated from own Node and processed. Does nothing if event comes from external Node.
ET_LIGHT_LEVEL	Event for internal use. In conjunction with AT_LIGHT_REGULATION in ReactionTab it defines the virtLum which belongs to the light regulation.
ET_SYSTEM_TIME	not used for now
ET_TIMER	Event is generated from own Node and processed. Needs a TimerTab entry
ET_REGULATION	Event can be used for initializing virtLums on other nodes for light regulation.
ET_EXT_BEACON	Event received by BRfirmware forwarded to BTfirmware. Has entry in eventTab.

8.12 Appendix L: Command description BR firmware ← BT firmware

PacketType 2

CommandTypeMsg	Cmd-No	Description	Parameter	Response	Encryption
GetLocalTime	0xE0 (224)	Request to BT-firmware to deliver actual Unix UTC local timestamp via SetLocalTime()	none	None The MWAYfirmware answers with Command <i>SetLocalTime</i> (Appendix B)	Node key
GetMyNodeID	0xE1 (225)	BT-firmware sets its node DestinationID	none	The MWAYfirmware answers with Command <i>SetNodeID</i> (Appendix B)	Node key
SetBeaconState	0xE2 (226)	VSfirmware informs MWAYfirmware about Beacon state as set in AT_BEACON_STATE param 0	Byte 0: State (0=Off, 1=On, 2=Toggle)	none	Node key

8.13 Appendix M: Use cases

8.13.1 BT Button Type and destinationType

A command from the App or an event from the App or the nodeDevice will deliver destinationType=01 (FROM_TO_MESH) within the MsgHeader.

If delivered from the App no sourceID can be used in the VSfirmware, since this will be dynamically tracked by the MWAYfirmware. An event from the App will not use any eventTab entries. However, if a Bluetooth Button will be used – this will be coupled with the one nodeDevice thru the MWAYfirmware. In this case the MsgHeader must contain destinationType=00 (FROM_LOCAL_NODE) if delivered to VSfirmware.

The following image may show, how a BT_BUTTON_TYPE_1 (coupled with nodeDevice#1) shall react on nodeDevice#2 (which has its own BT_BUTTON_TYPE_1).


reactionTab nodeDevice#1:
not nessacary

eventTab nodeDevice#1:
uint8_t active=0; //each Bit position declares on/off for inputNum0..7
uint8_t enableMesh=0b00000001; //each Bit position declares on/off for inputNum0..7
uint16_t eventType=0x0001;
uint16_t para=0x0000;

VSfirmware#1 verifies eventTab whether „enableMesh=1“. If so, a message with header **DestinationType=01** und **DestinationID=0x0002** will be delivered into BT mesh.

MWAYfirmware#2 receives the message and delivers to VSfirmware#2 with sourceID=0x0002, destinationID=0x0002, destinationType=01.

reactionTabnodeDevice#2:
uint16_t eventType=ET_BT_BUTTON_TYPE_1
uint16_t sourceID=0x0001
uint8_t inputNum=0
uint8_t actionTyp=1;
uint8_t userkeyID=0xFF;
uint8_t param[0..2]={virtLum#2,Scene_x,0}



8.13.2 Lightcontrol and motion monitoring

A stairway area shall have different luminaire brightness in dependence of a motion detection over time. In order to configure a stairway lighting system we need (for example) to configure one virtLum with its data:

- Create virtLum#1 Typ2 (R,G)
- Set phys lum channel R,G
- Set virtLum#1 Data:

Byte 1: dimSpeed (0..255) (700ms units) = 4

Byte 2: free

Byte 3: free

Byte 4: activeBrightness[step%]=254

Byte 5: passiveBrightness[step%]=127

Byte 6: basicBrightness[step%]=50

Byte 7: min brightness[step%]=0

Byte 8: time active= 5

Byte 9: time passive=7

To turn on virtLum with a Button we need something like this:

- SetScene (sceneNo=2...)
- SetReactionTab(ET_BUTTON,inputNum=1,AT_SCENE,userkeyID=0xff,param1=virtLum#1,param2=LLScene#2)

As soon AT_SCENE will act on virtLum#1 (via Event ET_BUTTON) the MODE_AUTO gets active (because a time active/passive has been configured).

If the lightcontrol passive time has been passed, „basicBrightness“ will set to output. With a signalization of the motion sensor, the virtLum#1 will output “activeBrightness” To obtain this, the following command need to be setup:

- Set ReactionTab ET_SENSE_MOVEMENT, on virtLum 1, Typ 2, AT_LIGHT_CONTROL with Param 4 = moveSenseAct: **MOVE_SENSE_ON_OFF**

Use

- SetInput ET_SENSE_MOVEMENT active

to start a stairway lighting control

8.13.3 Lightregulation

The regulation process has to analyze the set setpoint and the feedback to produce the output value of an output device.

Several deviceNodes in a BT-Mesh-Network may own several virtLums. However, for a light regulation we need to define

- 1) Which virtLums shall act as output device
- 2) Which deviceNode shall use its brightness sensor for the setpoint value and feedback value
- 3) How to activate the light regulation

8.13.3.1 Define which virtLums shall act as output device

An „output device“ consist at least in one virtLum. An „output device“ may consist in several virtLums. An „output device“ may consist even in several virtLums on different deviceNodes. However, the VSfirmware works internally with one „LRLum“ (LightRegulation-Luminaire) as an „output device“, which consist at least of one virtLum. To define a simple “output device” we need for example the following commands:

- NodeCreateVirtLum1, Typ2 (R,G)
- Set phys lum1 channel 1(adr1), channel2(adr2)
- Set virtLum1 Data: all NULL
- SetNodeScene2(50%,127r,127g)

For the VSfirmware „LRLum“ consist in the amount of entries in the reactionTab, here virtLum1:

entry	EventTyp	sourceID	inputNum	actionTyp	userNum	Para1:virtLumNo	Para2:LLscene
5	ET_LIGHT_LEVEL	0	0	AT_LIGHT_REGULATION	255	1	2

- SetNodeReactionEntry(ET_LIGHT_LEVEL,srcID=x,in=0,AT_LIGHT_REGULATION(virtLum1, **LLScene2**))
- SetNodeReactionEntry(ET_LIGHT_LEVEL,srcID=x,in=0,AT_LIGHT_REGULATION(virtLum2, **LLScene3**))
- SetNodeReactionEntry(ET_LIGHT_LEVEL,srcID=x,in=0,AT_LIGHT_REGULATION(virtLumX, **LLSceneX**)) etc.

The relation to a **LightLevelScene** is important for the later use of output value of virtLum1 of LRLum, without changing any color mood.

8.13.3.2 Define the output value – define the room brightness the lightregulation shall use

The output value of the „LRLum“ need to be defined. Meaning each defined virtLum (see above) should be adjusted to users satisfaction of a room brightness.

This can be done by simply using command „SetColorControl“ or define a comfortable slider which may not change the color mood, but the brightness:

- SetScene2VirtLum(virtLum=1,sceneNum=2)
- SetNodeReactionEntry(ET_SLIDER,srcID=0, inputNum=2, AT_SLIDER_CONTROL(virtLum1, SLIDER_TYPE_BRIGHTNESS), user=0xFF)

entry	EventTyp	sourceID	inputNum	actionTyp	userNum	Para1:virtLumNo	Para2:sliderType
3	ET_SLIDER(21)	0	2	AT_SLIDER_CONTROL	255	1	SLIDER_TYPE_BRIGHTNES(0)

Use e.g. „Send Event ET_SLIDER(inputNum=2,pos[=1..254])” to adjust output value...

8.13.3.3 Define the setpoint and start light regulation

If the output value(s) of the output device LRLum has been setup by the user (see above), the setpoint and the regulation start can be issued by:

- SetInput(ET_SENSE_BRIGHTNESS,active=1,mesh=0,inputNum=0,para=0xFFFF) mitgeteilt.

By receiving this command, the VSfirmware will

- Transfer the setpoint to „eventTab[ET_SENSE_BRIGHTNESSindex].para”.
- Start the LightRegulationTask by init LRLum first and output value on LRLum thereafter every 800ms.

8.14 Appendix N: CRC8

```
const uint8_t u8CRC8Table[256] = {
    0x00, 0x07, 0x0e, 0x09, 0x1c, 0x1b, 0x12, 0x15, 0x38, 0x3f, 0x36, 0x31, 0x24, 0x23, 0x2a, 0x2d,
    0x70, 0x77, 0x7e, 0x79, 0x6c, 0x6b, 0x62, 0x65, 0x48, 0x4f, 0x46, 0x41, 0x54, 0x53, 0x5a, 0x5d,
    0xe0, 0xe7, 0xee, 0xe9, 0xfc, 0xfb, 0xf2, 0xf5, 0xd8, 0xdf, 0xd6, 0xd1, 0xc4, 0xc3, 0xca, 0xcd,
    0x90, 0x97, 0x9e, 0x99, 0x8c, 0x8b, 0x82, 0x85, 0xa8, 0xaf, 0xa6, 0xa1, 0xb4, 0xb3, 0xba, 0xbd,
    0xc7, 0xc0, 0xc9, 0xce, 0xdb, 0xdc, 0xd5, 0xd2, 0xff, 0xf8, 0xf1, 0xf6, 0xe3, 0xe4, 0xed, 0xea,
    0xb7, 0xb0, 0xb9, 0xbe, 0xab, 0xac, 0xa5, 0xa2, 0x8f, 0x88, 0x81, 0x86, 0x93, 0x94, 0x9d, 0x9a,
    0x27, 0x20, 0x29, 0x2e, 0x3b, 0x3c, 0x35, 0x32, 0x1f, 0x18, 0x11, 0x16, 0x03, 0x04, 0x0d, 0x0a,
    0x57, 0x50, 0x59, 0x5e, 0x4b, 0x4c, 0x45, 0x42, 0x6f, 0x68, 0x61, 0x66, 0x73, 0x74, 0x7d, 0x7a,
    0x89, 0x8e, 0x87, 0x80, 0x95, 0x92, 0x9b, 0x9c, 0xb1, 0xb6, 0xbf, 0xb8, 0xad, 0xaa, 0xa3, 0xa4,
    0xf9, 0xfe, 0xf7, 0xf0, 0xe5, 0xe2, 0xeb, 0xec, 0xc1, 0xc6, 0xcf, 0xc8, 0xdd, 0xda, 0xd3, 0xd4,
    0x69, 0x6e, 0x67, 0x60, 0x75, 0x72, 0x7b, 0x7c, 0x51, 0x56, 0x5f, 0x58, 0x4d, 0x4a, 0x43, 0x44,
    0x19, 0x1e, 0x17, 0x10, 0x05, 0x02, 0x0b, 0x0c, 0x21, 0x26, 0x2f, 0x28, 0x3d, 0x3a, 0x33, 0x34,
    0x4e, 0x49, 0x40, 0x47, 0x52, 0x55, 0x5c, 0x5b, 0x76, 0x71, 0x78, 0x7f, 0x6a, 0x6d, 0x64, 0x63,
    0x3e, 0x39, 0x30, 0x37, 0x22, 0x25, 0x2c, 0x2b, 0x06, 0x01, 0x08, 0x0f, 0x1a, 0x1d, 0x14, 0x13,
    0xae, 0xa9, 0xa0, 0xa7, 0xb2, 0xb5, 0xbc, 0xbb, 0x96, 0x91, 0x98, 0x9f, 0x8a, 0x8d, 0x84, 0x83,
    0xde, 0xd9, 0xd0, 0xd7, 0xc2, 0xc5, 0xcc, 0xcb, 0xe6, 0xe1, 0xe8, 0xef, 0xfa, 0xfd, 0xf4, 0xf3
};
```

```
#define proccrc8(u8CRC, u8Data) (u8CRC8Table[u8CRC ^ u8Data])
```

Example:

```
...
for (uint8_t i=(11+headerData.addressLength); i<(11+headerData.addressLength+datLength); i++)
{
    crc = proccrc8(crc, UartBufferReadByteWithoutDel(i));
}
uint8_t crcData = UartBufferReadByteWithoutDel(11+headerData.addressLength+datLength);
```

```
if (crc != crcData)
{
    // Prüfsumme falsch
}
```

8.15 Appendix O: En- & Decryption

```
void XTEAEncipher( uint32_t * v, uint32_t * k)
{
    uint32_t v0=v[0], v1=v[1];
    uint32_t sum=0, delta=0x9E3779B9;
    for(uint8_t i=0; i<64; i++) {
        v0 += (((v1 << 4) ^ (v1 >> 5)) + v1) ^ (sum + k[sum & 3]);
        sum += delta;
        v1 += (((v0 << 4) ^ (v0 >> 5)) + v0) ^ (sum + k[(sum>>11) & 3]);
    }
    v[0]=v0; v[1]=v1;
}
//-----
void XTEADecipher( uint32_t * v, uint32_t * k)
{
    uint32_t v0=v[0], v1=v[1];
    uint32_t delta=0x9E3779B9;
    uint32_t sum = delta * 64;
    for(uint8_t i = 0; i < 64; i++)
    {
        v1 -= (((v0 << 4) ^ (v0 >> 5)) + v0) ^ (sum + k[(sum>>11) & 3]);
        sum -= delta;
        v0 -= (((v1 << 4) ^ (v1 >> 5)) + v1) ^ (sum + k[sum & 3]);
    }
    v[0]=v0; v[1]=v1;
}
```

Example:

```
uint32_t nodeKey[4] = {0x12345678,0x12345678,0x12345678,0x12345678};
...
    if (addrData.encryptionType == NODE_KEY_TYP)
    {
        for (uint16_t i=0; i<datLength; i+=8)
        {
            XTEADecipher((uint32_t *) (dataPointer+i), nodeKey);
        }
    }
```

8.16 Appendix P: Sequence table definition

The sequence table in the node can hold up to 64 entries. A sequence consist in presenting several light level scene's, separated by a pause time, on one virtLum (FunctionalGroup). At the end of a sequence a jump to the beginning (loop) and / or an event can be send into mesh. The sequence table can be filled with the command "SetSeqEntry(sceneNo,pause,next)". The FunctionalGroup need to be assigned in the ReactionTab.

The variable "next" controls next action to be performed and consist in next = 0xESxxx xxxx.

E = Event-Bit: setting this bit will send an event into mesh and indicates end of a sequence

S = Stop-Bit: setting this bit will stop the sequence, otherwise will start sequence from beginning (loop)

X = 0..3F, next index in sequence table

Example:Loop

Sequence name	Seq index	Scene No.	pause	Next	action
A	0	1	3	0x01	Set scene 1 to FunctionalGroup and pause ca. 2 sec
A	1	2	4	0x02	Set scene 2 to FunctionalGroup and pause ca. 3 sec
A	2	5	7	0x00	Set scene 5 to FunctionalGroup, pause ca. 10 sec, loop to seqIndex 00

Example:Loop and sending an event

Sequence name	Seq index	Scene No.	pause	Next	action
A	0	1	3	0x01	Set scene 1 to FunctionalGroup and pause ca. 2 sec
A	1	2	4	0x02	Set scene 2 to FunctionalGroup and pause ca. 3 sec
A	2	5	7	0x80	Set scene 5 to FunctionalGroup, pause ca. 10 sec, send an event ET_SEQUENCE and loop to seqIndex 00

Example:stop

Sequence name	Seq index	Scene No.	pause	Next	action
A	0	1	3	0x01	Set scene 1 to FunctionalGroup and pause ca. 2 sec
A	1	2	4	0x02	Set scene 2 to FunctionalGroup and pause ca. 3 sec
A	2	5	7	0x40	Set scene 5 to FunctionalGroup, pause ca. 10 sec, stop sequence

Example:stop and sending an event

Sequence name	Seq index	Scene No.	pause	Next	action
A	0	1	3	0x01	Set scene 1 to FunctionalGroup and pause ca. 2 sec
A	1	2	4	0x02	Set scene 2 to FunctionalGroup and pause ca. 3 sec

Sequence name	Seq index	Scene No.	pause	Next	action
A	2	5	7	0xC0	Set scene 5 to FunctionalGroup, pause ca. 10 sec, send an event ET_SEQUENCE and stop sequence

Example: sequence A sends event to start sequence B

Sequence name	Seq index	Scene No.	pause	Next	action
A	0	1	3	0x01	Set scene 1 to FunctionalGroup and pause ca. 2 sec
A	1	2	4	0x02	Set scene 2 to FunctionalGroup and pause ca. 3 sec
A	2	5	7	0xC0	Set scene 5 to FunctionalGroup, pause ca. 10 sec, send an event ET_SEQUENCE and stop sequence

Sequence name	Seq index	Scene No.	pause	Next	action
B	3	4	3	0x04	Set scene 1 to FunctionalGroup and pause ca. 2 sec
B	4	6	4	0x05	Set scene 2 to FunctionalGroup and pause ca. 3 sec
B	5	9	7	0x40	Set scene 5 to FunctionalGroup, pause ca. 10 sec and stop sequence

Note:

- The Stop-Bit is also set, if "0x7e" is delivered by CMD_SET_SEQUENCE_ENTRY
- A scene has been completed if its fading time has been reached and a pause will be start thereafter.
- Stopping all sequence on a nodeDevice button, is possible via a proper reactionTab entry.
- Stopping a specific sequence on a FunctionalGroup is possible via manual user access (button) on that FunctionalGroup.
- A running sequence onto a FunctionalGroup is in MODE_SEQUENCE
- A FunctionalGroup which is in MODE_SEQUENCE cannot be used for light regulation or light time control (active, passive, basic).
- Sending an ET_SEQUENCE is possible at sequence **end position** only
- An ET_SEQUENCE can trigger another sequence on a different nodeDevice

Running sequences as a sequence chain on different FunctionalGroup on a single nodeDevice is possible and described in "Timer&DT8.pdf" Docu (P1104-03-S).

8.17 Appendix Q: Time calculation according DALI

Several time values are represented by a 1 byte value. The used range for this value is 0 ...33.

The following formula has to be used to get the real time value in seconds:

$$t_1 = -1 + 1.4^x$$

Examples

$$x = 5$$

$$t_1 = -1 + 1.4^5 = 4.37824 \text{ seconds}$$

$$x = 33$$

$$t_1 = -1 + 1.4^{33} = 66407.7 \text{ seconds} = 18.4 \text{ hours}$$

<u>x</u>	<u>time[s]</u>
1	0,400
2	0,960
3	1,744
4	2,842
5	4,378
6	6,530
7	9,541
8	13,758
9	19,661
10	27,925

etc.

8.18 Appendix R: Timer Handling

A node Device can hold up to 32 timer settings. A timer expires, if the actual timestamp matches the timestamp configured by the user due to **SetTimer**. Resolution is 1 minute. A time target setting can be triggered up to a week. A repetitive trigger setting (daily, weekly) is possible.

Description of SetTimer parameter

Byte 0	indicates the timer number [1..32]
Byte 1-4	initial local Unix timestamp (UTC). Once a timer elapsed, this value will be updated by VSfirmware if repetition is required
Byte 5	Weekday field where Bit0..Bit6 indicates Monday..Sunday,
Byte 6	<p><u>Repetitive control</u>: Bit0=daily, Bit1=weekly If either “daily” or “weekly” false, the timer elapsed once within the setting of hour and minute. If “daily” true, the timer elapsed within the setting of hour and minute every day (ignores weekday field). If “weekly” true, each day set in “weekday field” will be used as the time target every week If both “daily” and “weekly” true, weekly will be ignored.</p> <p><u>Mesh event</u>: send event to mesh: Bit4 Setting bit4 forces B2L-App to integrate Timer N in its EventConfiguration. This allows actions on other deviceNodes. Re-setting this bit forces B2L-App to delete the Timer N EventConfiguration and possible reactionTab entry(ies).</p> <p><u>Enable/Disable Timer</u>: Bit5 Setting this bit forces the Timer N to process its task. Re-setting this bit forces the Timer N not to process its task.</p>

If a repetitive programmed Timer elapsed, the TimerTab entry is always valid for the future.

If a non-repetitive programmed Timer elapsed, the TimerTab entry needs to be rejected by B2L- and/or T4L-App !

If the actual timestamp greater or equal the programmed time target, an action will be performed. Several actions maybe processed in this case, if the actual timestamp is invalid for a longer time...

Examples:

Set a Timer 1 to fixed datetime 02.08.2018 15:00, set mesh event

“02.08.2018 15:00” => 1533222000

Byte 0: 1

Byte 1-4: Time => 1533222000 (dezimal)

Byte 5: 0x0000 0000

Byte 6: xx11 xx00

Set a Timer 2 to daily at 12:00, no mesh event

"01.01.1970 12:00" => 43200

Byte 0: 2

Byte 1-4: 43200 (dezimal)

Byte 5: 0

Byte 6: xx10 xx01

Set a weekly Timer 3, every Tuesday and Thursday at 08:00, no mesh event:

"01.01.1970 08:00" => 28800

Byte 0: 3

Byte 1-4: 28800(dezimal)

Byte 5: 0x0000 1010 (Tuesday, Thursday)

Byte 6: xx10 xx10 (x=unused)

8.19 Appendix S: Testing the sensor (DUT) in the tester

For testing a device with the BlueRangeNode firmware (DUT) in the tester in the VS-production, it is necessary to establish a GATT-connection to make testing of the DUT possible. The data shall be sent from the PC within the tester. There are two possibilities:

1. Establish a connection from a 2nd module (e.g. Multisensor XS) which has already been tested and which working by connecting it via an USB-UART-adaptor and establishing a GATT-connection from the PC to the DUT by using the module and sending some user defined commands to check the functionality of the DUT.
2. Establish a GATT-connection from a nRF52-DK (evaluation-kit) which is connected to the tester PC via USB and establish a connection to the DUT with the help of the nRF52-DK.

If the solution in point 1 will be used, the config of the BT module inside the modified Multisensor XS in the tester must be adapted by M-Way, so that proper testing can be performed.


If the solution in point 2 will be used, a working configuration for the nRF52-SDK will be supplied by M-Way.

The following graphics show the possible test-cases in the tester:

1. Using a 2nd device (e.g. modified Multisensor XS):



2. Using a "nRF52-DK" (evaluation-kit) in the tester:



The following ASCII-commands have been defined for establishing a connection or disconnecting a modified Multisensors XS or nRF52-DK via GATT from the DUT:

Msg	Description	Parameter	Response	Encryption
MakeGattConnection	Establish a GATT-connection to the DUT	BLE-GAP-Address, Serial number, Node Key.	OK (Connection successful) FAIL (Connection not successful)	none
DisconnectGatt	Disconnect an existing connection from the DUT	none	OK (Disconnected successfully)	none

If a GATT-connection is established, the defined events and reactions from the document shall be valid (like an APP-connection to the DUT). VS prefers the solution with the nRF52-DK, because it is already used for programming the BT module of the DUT.

8.20 Appendix T: StartUp nodeDevice and lightlevel on a virtLum

8.20.1 Power Ready

The MWAYfirmware must wait for its bluetooth communication until its detection of ET_POWER_READY (sending by VSfirmware). This becomes necessary because of power absorption if bluetooth communication becomes true.

The VSfirmware checks its μ C-voltage-power first and will send ET_POWER_READY as soon power has been stabilized.

While ET_POWER_READY has not been received by the MWAYfirmware, the MWAYfirmware itself should request this event via ET_POWER_READY every 100ms. On request, the VSfirmware may send either ET_POWER_READY(0) or ET_POWER_READY(1).

If the event ET_POWER_READY(1) could not be received within 2 seconds by the MWAYfirmware, the controller may start its bluetooth communication nevertheless.

8.20.2 Default Scene

Create a default LLScene#1 if not exist. LLScene#1 can of course be overwritten by the user.

```
#define DEFAULT_BRIGHTNESS_SCENE (127)
```

```
#define DEFAULT_TIM2TARGET_SCENE (0)
```

```
#define DEFAULT_CHAN0_SCENE (254)
```

```
#define DEFAULT_CHAN1_SCENE (254)
```

```
#define DEFAULT_CHAN2_SCENE (254)
```

```
#define DEFAULT_CHAN3_SCENE (254)
```

```
#define DEFAULT_CHAN4_SCENE (254)
```

```
#define DEFAULT_CHAN5_SCENE (254)
```

8.20.3 Virtual Luminaire, Functional Group (FG)

Each FG which has been channel configured, may react in its lightlevel, depending of the action within the reactionTab. The output lightlevel of a FG is prioritized as shown in the following tab:

Prio	Event	Scene num, shown in	% - Lightlevel as shown in	Mode setting	Init activeTime
1	Timer (if < localTime), light regulation start	reactionTab entry	eventTab[LIGHT_REGULATION]	auto	y
2	Timer (if < localTime), auto switch	reactionTab entry	FG parameter activeLL	auto	y
3	Timer (if < localTime), manual switch	reactionTab entry	sceneTab: sceneLL	manual	n
4	Timer (if < localTime), Sequence, start	reactionTab entry	sequenceTab: sceneLL	sequence	n
5	Timer / Auto switch	reactionTab entry	FG parameter basicLL	auto	n
6	Movement sense	reactionTab entry	FG parameter basicLL	auto	n
7	Brightness sense, light regulation	reactionTab entry	eventTab[LIGHT_REGULATION]	auto	y

8	Manual switch	reactionTab entry	sceneTab: sceneLL	manual	n
9	Sequence switch	reactionTab entry	sequenceTab: sceneLL	sequence	n
10	FG exist, but no reaction programmed	-	0 %	manual	n

8.20.4 Changing reactionTab during user event configuration

After power up several FG's may have its specific output lightlevel. A change of the reactionTab afterwards may automatically change the outputlevel of the specific FG in the same way as stated in the tab above.

8.21 Appendix U: virtual luminaire data

Following data need to be placed in the APP during creation of a virtual luminaire type:

Byte 0: Number Virtual Luminaire(1..16)

User selection of the virtual luminaire number 1..16 of the own node. We start with 1, since internally the VSfirmware uses "0" for internal checks. However, this applies for most other vars too.

Byte 1: dimSpeed (0..255)

Needed for manual dimming up/down. Internally this number will be used in units of 700ms. One step down uses a deltaDALI value to output next lightlevel. "deltaDali" corresponds to "stepCount" ([see Appendix C](#)) within 700ms. If the user wants to delay further more this behaviour, he can do it with "dimSpeed". A "1" will show up the lightlevel within 1400ms. A "10" will show up the next lightlevel smoothly within 70700ms.

Byte 2: reserved1

Byte 3: reserved2

Byte 4: active brightness[step%]

A virtual luminaire belongs to a light regulation if "light regulation active = 1" and if it is in "active" state. The user may select a number between 0..100 (%) while the MWAYfirmware sends 0..254 (step%) to the VSfirmware.

Byte 5: passive brightness[step%]

While a virtual luminaire is in "active" state for "time active" it will change its "active brightness" to "passive brightness". Also it will be rejected for a light regulation if so. A movement sensor sense may recall the "active" state.

Byte 6: basic brightness[step%]

While a virtual luminaire is in "passive" state for "time passive" it will change its "passive brightness" to "basic brightness". Also it will be rejected for a light regulation if not already done so. A movement sensor sense may recall the "active" state.

Byte 7: min brightness[step%]

There is a “min brightness” which will be evaluated from all the DALI-driver which are configured within the virtLum type and its physical luminaire connections. The VSfirmware may retrieve this value by “GetVirtLumData” as soon the virtLum has been fully configured with its phys channels. The user may increase the value in the App but not decrease.

Byte 8: time active

A value “0” will never reach a “passive” state. A value > 0 will switch to “passive” state after the “active” time has been expired (otherwise another event will retrigger the “active” time)

Byte 9: time passive

A value “0” will never reach a “basic” state. A value > 0 will switch to “basic” state after the “passive” time has been expired (otherwise another event will retrigger the “active” time)

8.22 Appendix V: moveSenseAct

This variable is used as a parameter for AT_LIGHT_CONTROL. If a movement sensor shall act on light time / light regulation with a virtLum.

An ET_SENSE_MOVEMENT Event may act in conjunction with AT_LIGHT_CONTROL in various ways:

#define MOVE_SENSE_UNKOWN 0

Description: action not initialized / movement sensor may not available

#define MOVE_SENSE_ON_OFF 1 (AKTOR_FUNKTION_SENSOR_BEWEGUNG_ON_OFF)

Description: sets lightlevel to activeLL, retriggers activeTime

#define MOVE_SENSE_OFF 2 (AKTOR_FUNKTION_SENSOR_BEWEGUNG_OFF)

Description: same as MOVE_SENSE_ON_OFF, but: if basicLL has been reached no action should be performed on the virtLum.

#define MOVE_SENSE_PASSIV 3 (AKTOR_FUNKTION_SENSOR_BEWEGUNG_PASSIV)

Description: switches virtLum to “passivLL”, if virtLum outputs basicLL. Retrigger passiveTime.

#define MOVE_SENSE_MANUAL 4 (AKTOR_FUNKTION_LICHTWERT)

Description: switches virtLum to “activeLL“, turns off light time control.

8.23 Appendix W: Search modes

#define CLEAR_AND_SEARCH 0

Clear & Search:

- resets all virtLums,
- erases all internal LED driver group addresses,
- resets all DALI driver short addresses,
- starts generic search of connected LED driver and saves its short address

Command “GetPhysLumSearch” informs about all available phys lum driver in a 64-Bit variable.

#define ADD_ONLY_UNADDRESSED 1

Search only New:

- starts generic search of connected LED driver which have not been assigned to a short address
- saves an eventually new short address
- does not change a virtLum configuration

Command “GetPhysLumSearch” informs about new available phys lum driver channels in a 64-Bit variable.

#define ADD_ONLY_UNADDRESSED_DOUBLE 2

Keep & Search:

- starts generic search of connected LED driver which have not been assigned to a short address
- saves an eventually new short address
- checks if a driver contains a double assigned physical address (this is possible, if a user connects a new physical lum which owns already the same physical address of another one). If so, this channel address will be reset and new addresses will be given. This follows that a virtLum could be assigned to different physical channel address prior of this search!

Command “GetPhysLumSearch” informs about new available phys lum driver channels after last search in a 64-Bit variable. If double address found, this address will be reflected as “new” since it cannot be assigned to an eventually created previous virtLum with that address.

Command „GetNodePhysLum“ informs about each available physical driver channel addresses.

8.24 Appendix X: Slider Type

A slider type indicates the handling / calculation of a virtLum's phys channel.

A reactionTab entry ET_SLIDER, inputNum should be connected to an action AT_SLIDER_CONTROL(virtLum, sliderTyp). The entrance of an ET_SLIDER(pos, inputNum) would then react on the defined sliderTyp as follows:

#define SLIDER_TYPE_BRIGHTNESS 0

The brightness of the specified virtLum (meaning all its available channels) will be adjusted according to the brightness slider position.

#define SLIDER_TYPE_SINGLE 1

The R-channel of the specified virtLum will be adjusted according to its position.

#define SLIDER_TYPE_TUNABLE_WHITE 2

The RG-channel of the specified virtLum will be calculated in VSfirmware according to its position:

Position = 127 → R=127, G=127

Position = 128 → R=126, G=129

Position = 100 → R=100, G=154

Position = 0 → R=0, G=254

Position = 254 → R=254, G=0

#define SLIDER_TYPE_RGB 3

The RGB-channel of the specified virtLum will be calculated according to its position:

Not available yet

#define SLIDER_TYPE_RGBW 4

The RGBW-channel of the specified virtLum will be calculated according to its position:

Not available yet

#define SLIDER_TYPE_RGBWA 5

The RGBWA-channel of the specified virtLum will be calculated according to its position:

Not available yet

#define SLIDER_TYPE_RGBWAF 6

The RGBWAF-channel of the specified virtLum will be calculated according to its position:

Not available yet

#define SLIDER_TYPE_LIGHT_REGULATION 7

As SLIDER_TYPE_BRIGHTNESS: For each virtLum detected in reactionTab with ET_LIGHT_LEVEL and AT_LIGHT_REGULATION

A reactionTab entry ET_SLIDER_CONTROL connected with an action AT_SLIDER_CONTROL ignores the sliderTyp but sets each available virtLum channel according to its ET_SLIDER_CONTROL parameter. This is an adaption of the command “SetColorControl”.

	<u>Event ET SLIDER</u>	<u>Event ET SLIDER CONTROL</u>
SLIDER_TYPE_BRIGHTNESS	Ok (act on brightness level of FunctionalGroup(s) which owns the scene number)	Untested (act on all channels, no scene relation)
SLIDER_TYPE_SINGLE	Ok (act on R-channel (channel 1) of FunctionalGroup(s) which owns the scene brightness level)	Untested (act on R-channel in conjunction with brightness level, no scene relation)
SLIDER_TYPE_TUNABLE_WHITE	Ok (act on RG-channel (channel 1&2) of FunctionalGroup(s), no scene relation)	Untested (act on RG-channel in conjunction with brightness level, no scene relation)
SLIDER_TYPE_RGB	Not implemented	Ok (act on RGB channels, no scene relation)
SLIDER_TYPE_RGBW	Not implemented	Ok (act on RGBW channels, no scene relation)
SLIDER_TYPE_RGBWA	Not implemented	Not implemented, from App
SLIDER_TYPE_RGBWAF	Not implemented	Not implemented, from App

8.25 Appendix Y: Bootloader

A new VSfirmware consist in a binary encrypted file, which will be generated by VS. This “BTSensorV00000000.bin” file will be delivered to M-Way to generate a new Tablet-/Handy “LINA”-App. This binary file consist in

Address	0	1	2	3	4	5	6	7	8	9	a	b	c	d	e	f
00000000	00	00	00	00	00	00	01	10	00	01	e0	00	01	e0	00	00
00000010	01	00	00	00	00	00	ae	e5	06	23	ed	5c	6e	7b	97	65
00000020	78	63	67	15	55	97	12	4d	92	fc	50	ed	d0	4a	12	4d
00000030	92	fc	50	ed	d0	4a	12	4d	92	fc	50	ed	d0	4a	1e	1a
00000040	3e	fa	51	aa	37	00	12	4d	92	fc	50	ed	d0	4a	ca	57
00000050	8f	92	d0	d2	93	4b	74	b4	6b	b5	12	c3	ce	e4	74	b4
00000060	6b	b5	12	c3	ce	e4	5c	f2	7c	67	63	59	c9	57	7a	c4
00000070	e4	51	1f	96	ac	18	d0	0c	b1	27	ad	e8	1d	76	57	71
00000080	07	c2	ac	90	97	31	01	36	b1	84	fd	fd	2e	97	eb	65
00000090	cd	d1	1e	ec	92	78	99	3e	d3	4a	0d	74	34	ec	2e	75
000000a0	cf	fb	c0	ae	77	58	61	85	bc	4c	11	9b	d1	7b	1e	1a
000000b0	3e	fa	51	aa	37	00	74	b4	6b	b5	12	c3	ce	e4	74	b4
000000c0	6b	b5	12	c3	ce	e4	46	c9	81	eb	04	ee	90	0c	5c	bb
000000d0	9a	f0	c4	b4	bc	70	47	e4	b6	29	3c	20	bc	5c	8f	2a
000000e0	5b	50	ad	ab	eb	07	b0	3a	93	ce	37	e7	65	51	ad	7d
000000f0	6d	08	48	21	41	28	cf	c4	eb	cb	d2	e1	ae	13	18	a4
00000100	d8	b7	78	ba	b0	20	ff	78	02	a4	1a	8f	9a	77	da	57
00000110	14	1b	64	90	23	3a	26	6c	00	01	e0	00	01	e0	00	01
00000120	01	00	00	00	00	00	a1	aa	b4	03	bd	0d	dc	56	1c	b6
00000130	1e	55	28	1b	0c	4e	04	00	04	00	10	10	10	10	10	10

Byte 0..3:

4 Bytes version number

Byte 4..7:

4 Bytes block length = page_size 256 + firmware_size 4 + blocks_total 2 + current_block 2 + block_size 2 + block_startaddr 4 + CRC 2 = 272 == 0x00000110

Byte 8..nn

All data as a stream

At the end "EEEE" 0x45454545 as „EOF“

The encrypted VSfirmware File need to be delivered via command “TransmitFirmwareData” and looks like this:

00000000 00000110 (unverschlüsselt)

0001e000 01e0 0000 0100 00000000 (unverschlüsselt) aee50623...”CCCC”

0001e000 01e0 0001 0100 00000000 (unverschlüsselt) a1aab403...”CCCC”

...

45454545

The data stream needs to be delivered by “TransmitFirmwareData”, for example:


TransmitFirmwareData (Firmware Size = 0001e000, Blocks Total = 01e0,Current Block = 0000, Block Size=0100, Block Start Address = 00000000, encrypted Block Data = aee50623...CCCC)

TransmitFirmwareData (Firmware Size = 0001e000, Blocks Total = 01e0,Current Block = 0001, Block Size=0100, Block Start Address = 00000000, encrypted Block Data = a1aab403...CCCC)

...

Note that Block Start Address is reserved and contains “00000000”.

The version number “00000000” need not to be delivered since it indicates a change, the file is organized.



8.26 Appendix Z: VS Internal Commands for Tester

We defined 2 commands to handle the function test of our devices inside the function tester.
They are only used for tester or debug purposes and needs no configuration !!!

A. SendRawData (type, data1, data1+x ... data7)

This command is used to send data over the lighting control interface of the device (ex. DALI) .

Byte 0 describes the type of data (example 0x00 = DALI)
Currently, we have only the type 'DALI'. More types can be defined in future.

For Type 'DALI', we use a similar protocol as our VS DALI Protocol, which is further described in document 'VS DALI protocol'.

Normal DALI command 'Off', broadcast

Bit count Decimal / hexadecimal	Repeat (after x ms)	Answer expected after x ms	DALI Byte 1	DALI Byte 2	Reserved
16 / 0x10	0	0	0xFE	0x00	

Repeated DALI command 'Reset', broadcast

Bit count	Repeat (after x ms)	Answer expected after x ms	DALI Byte 1	DALI Byte 2	Reserved
16 / 0x10	0x65	0	0xFF	0x20	

DALI command with Answer (Query) : 'QueryStatus', broadcast

Bit count	Repeat (after x ms)	Answer expected after x ms	DALI Byte 1	DALI Byte 2	Reserved
16 / 0x10	0	0x65	0xFF	0x90	

DALI Answer (Query) , received as BT_Response

MsgStatus	Bit count	Time till answer (ms)	Error code	DALI Answer Byte
	8 / 0x08	0x75	0x00	0xFF

DALI Error codes:	0	Message (no error)
	1	Time Out
	2	Frame Error
	3	Overlayed Answer

B. GetSensorData () -> Response : MsgStatus, MovementStatus (1Byte), Brightness (2 Bytes)

The command GetSensorData requests the actual state of the movement sensor and brightness value of the brightness sensor and send it back by response. This will need no special preparation / configuration of the sensor before !

Byte 0: CmdNo

Byte 1:MsgStatus

Byte 2: updateLevel MSB

Byte 3: updateLevel LSB

If MULTISENSOR:

Byte 4: Movement State

Byte 5..6: Brightness value

If CONNECT

Byte 4: 0x0000 0nn0

Bit 1: Button 1 pressed

Bit 2: Button 2 pressed

Byte 5..6: 0

C. UART-Test-Frame

This UART-frame can be used to test UART communication from/to BT module.